

INScore OSC Messages Reference v.1.31

D. Fober
<fober@grame.fr>



GRAME

Centre national de création musicale

INScore makes use of the following technologies:

The GUIDOEngine	http://guidolib.sf.net
The IRCAM Gesture Follower	http://imtr.ircam.fr/imtr/Gesture_Follower
The GRAME Faust Compiler	http://faust.grame.fr
The Qt5 cross-platform application and UI framework	https://www.qt.io/

INScore research and development has been funded by the French National Research Agency [ANR] Interlude project [ANR- 08-CORD-010] and INEDIT project [ANR-12-CORD-0009].

Contents

1	Introduction	2
2	General format	3
2.1	Parameters	3
2.2	Address space	4
2.3	Aliases	4
2.3.1	Scaling	5
2.3.2	Using more than one implicit message	5
3	Common messages	7
3.1	Positioning	8
3.1.1	Absolute positioning	9
3.1.2	Relative positioning	9
3.1.3	Components origin	10
3.2	Components transformations	10
3.3	Color messages	11
3.3.1	Absolute color messages	11
3.3.2	The color messages	12
3.3.3	The hsb messages	12
3.3.4	Relative color messages	13
3.4	Pen control	13
3.5	The 'effect' messages	14
3.5.1	The blur effect	14
3.5.2	The colorize effect	15
3.5.3	The shadow effect	15
3.6	The 'edit' message	15
4	Time management messages	17
4.1	Date and duration	17
4.2	Tempo	18
5	Miscellaneous messages	19
6	The 'set' message	20
6.1	Symbolic music notation	20
6.2	Piano roll music notation	21
6.3	Textual components	21
6.4	Vectorial graphics	22
6.5	Signals and graphic signals	23

6.6	Media files	23
6.7	Miscellaneous	24
6.8	File based resources	24
6.9	The file type	25
6.10	Web objects	25
7	The 'get' messages	27
8	Type specific messages	28
8.1	Brush control	28
8.2	Width and height control	29
8.3	Symbolic score	30
8.4	Piano roll	30
8.5	Audio and Video	32
8.6	SVG Objects	33
8.7	Rectangles	33
8.8	Arcs	33
8.9	The 'grid' object	34
8.10	Arrows	34
8.11	Textual objects	35
	8.11.1 Font control	35
	8.11.2 Writing	36
8.12	The 'debug' nodes	36
9	Application messages	37
9.1	Application management	37
9.2	Ports management	38
9.3	System support	38
9.4	Application level queries	39
9.5	Application static nodes	39
	9.5.1 The 'stats' nodes	39
	9.5.2 The 'debug' nodes	40
	9.5.3 The 'log' nodes	40
	9.5.4 The 'plugins' nodes	41
	9.5.5 The 'ssl' node	41
10	Scene messages	42
10.1	Scene control	42
10.2	OpenGL rendering	43
10.3	Scene queries	43
11	Messages forwarding	45
11.1	Remote hosts list	45
11.2	SSL support	46
11.3	Filters	46
11.4	Specific queries	47
12	Layers	48
12.1	Layers generalization	48

13 Mapping graphic space to time space	49
13.1 The 'map' message	49
13.1.1 Segments definitions	50
13.2 The 'map+' message	51
13.3 Mapping files	52
13.4 Symbolic score mappings	52
14 Synchronization	53
14.1 Synchronization modes	54
14.1.1 Using the master date	54
14.1.2 Synchronizing an object duration	55
14.1.3 Controlling the slave position	55
14.1.4 The syncFrame mode	55
15 Signals and graphic signals	56
15.1 The 'signal' static node.	56
15.1.1 Signal messages.	57
15.1.2 Composing signals in parallel.	57
15.1.3 Distributing data to signals in parallel	58
15.2 Connecting signals to graphic attributes.	59
15.3 Graphic signals.	60
15.3.1 Graphic signal default values.	61
15.3.2 Parallel graphic signals.	62
16 Sensors	63
16.1 Sensors as signals	63
16.2 Sensors as nodes	64
16.3 Values	64
16.4 Calibration	65
16.5 Sensor common messages	65
16.6 Sensor specific messages	66
16.6.1 Accelerometer sensor	66
16.6.2 Magnetometer sensor	67
16.6.3 Rotation sensor	67
16.6.4 Orientation sensor	67
16.6.5 Tilt sensor	67
17 Events and Interaction	68
17.1 Internal events	69
17.1.1 Mouse events	69
17.1.2 Touch events	70
17.1.3 Time events	70
17.1.4 Keyboard events	70
17.1.5 MIDI events	71
17.1.6 URL events	71
17.1.7 Miscellaneous events	71
17.1.8 Type specific events	72
17.2 Attribute based events	72
17.3 User defined events	73

17.4	The 'event' message	73
17.5	Variables	74
17.5.1	Position variables	74
17.5.2	Sensor variables	75
17.5.3	Time variables	75
17.5.4	Miscellaneous variables	75
17.5.5	Message based variables	76
17.5.6	Variables for user defined events	76
17.5.7	OSC address variables	76
17.6	Interaction state management	76
17.7	File watcher	77
18	Score expressions	78
18.1	General Syntax	78
18.2	Score Operators	78
18.3	Score Arguments	79
18.4	'expr' commands	80
18.5	newData event	80
19	Plugins	82
19.1	FAUST plugins	82
19.1.1	Set Message	82
19.1.2	Specific messages	83
19.1.3	Feeding and composing FAUST processors	83
19.2	Gesture Follower	84
19.2.1	Basic principle	84
19.2.2	Messages	84
19.2.3	Gestures management	85
19.2.4	Events and interaction	86
19.2.5	Gesture Follower Appearance	87
19.3	Httpd server plugin	87
19.3.1	Set Message	87
19.3.2	Specific messages	87
20	Changes list	89
20.1	Version 1.31 vs version 1.28	89
20.2	Version 1.28 vs version 1.27	89
20.3	Version 1.27 vs version 1.24	89
20.4	Version 1.24 vs version 1.22	90
20.5	Version 1.22 vs version 1.21	90
20.6	Version 1.21 vs version 1.18	90
20.7	Version 1.18 vs version 1.17	91
20.8	Version 1.17 vs version 1.15	91
20.9	Version 1.15 vs version 1.12	92
20.10	Version 1.12 vs version 1.08	92
20.11	Version 1.08 vs version 1.07	93
20.12	Version 1.07 vs version 1.06	93
20.13	Version 1.06 vs version 1.05	93

20.14	Version 1.05 vs version 1.03	94
20.15	Version 1.03 vs version 1.0	94
20.16	Version 1.00 vs version 0.98	94
20.17	Version 0.98 vs version 0.97	95
20.18	Version 0.97 vs version 0.96	95
20.19	Version 0.96 vs version 0.95	95
20.20	Version 0.95 vs version 0.92	95
20.21	Version 0.92 vs version 0.91	95
20.22	Version 0.91 vs version 0.90	96
20.23	Version 0.90 vs version 0.82	96
20.24	Version 0.82 vs version 0.81	96
20.25	Version 0.81 vs version 0.80	96
20.26	Version 0.80 vs version 0.79	96
20.27	Version 0.79 vs version 0.78	96
20.28	Version 0.78 vs version 0.77	97
20.29	Version 0.77 vs version 0.76	97
20.30	Version 0.76 vs version 0.75	97
20.31	Version 0.75 vs version 0.74	97
20.32	Version 0.74 vs version 0.63	97
20.33	Version 0.63 vs version 0.60	98
20.34	Version 0.60 vs version 0.55	98
20.35	Version 0.55 vs version 0.53	98
20.36	Version 0.53 vs version 0.50	99
20.37	Version 0.50 vs version 0.42	99

Chapter 1

Introduction

INScore is an environment for the design of augmented, interactive, dynamic musical scores, oriented towards unconventional uses of music notation and representation, including real-time symbolic notation capabilities. This environment is fully controllable using Open Sound Control [OSC] messages. This document presents all the messages supported by the system.

A scripting language has been defined as an extended textual version of OSC messages that allows you to design scores in a modular and incremental way. This language is close to the present specification. Its syntax and grammar are described in a separate document.

Note


Throughout the documentation, the sample code are given using scripting syntax i.e. that OSC messages are suffixed with a semi-colon ';'. This semi-colon is used as a message separator in INScore scripts and is not needed when sending messages over a network. See the INScore language reference for more information.

Chapter 2

General format

An OSC message is made of an OSC address, followed by a message string, followed by zero to n parameters. The message string could be viewed as the method name of the object identified by the OSC address. The OSC address could be string or a regular expression matching several objects.

OSCMessage



EXAMPLE


Sending the message x to the object which address is /ITL/scene/score with 0.5 as parameter.

```
/ITL/scene/score x 0.5;
```

The address is similar to a Unix path and supports regular expressions as defined by the [OSC specification](#). This address scheme is extended to address any host and applications (see section 17 p.68).


NOTE A valid legal OSC address always starts with /ITL that is the application address and that is also used as a discriminant for incoming messages.

OSCAddress



Identifiers may include letters, hyphen, underscore and numbers (apart at first position for the latter).

identifier



Some specific nodes (like *signals* - see section 15.1.1) accept OSC messages without message string:

SigOSCMessage



2.1 Parameters

Message parameters types are the OSC types *int32*, *float32* and *OSC-string*. In the remainder of this document, they are used as terminal symbols, denoted by **int32**, **float32** and **string**.

When used in a script file, **string** should be single or double quoted when they include characters not allowed in identifiers (space, punctuation marks, etc.). If an ambiguous double or single quote is part of the string, it can be escaped using a `'\'`.

Parameters types policy is relaxed: the system makes its best to convert a parameter to the expected type, which depend on the message string. With an incorrect type and when no conversion is applied, an incorrect parameter message error is triggered.

The system is strict regarding the number of expected parameters.

2.2 Address space

The OSC address space is made of static and dynamic nodes, hierarchically organized as in figure 2.1:




Figure 2.1: The OSC address space. Nodes in italic/blue are dynamic nodes.

OSC messages are accepted at any level of the hierarchy:

- **the application level** responds to messages for application management (udp ports management, loading files, query messages).
- **the scene level** contains *scores* that are associated to a window and respond to specific scene management messages. It includes a static node named *stats* that collects information about incoming messages, a static *log* node that control an embedded log window.
- **the component level** contains the score components and 3 static nodes:
 - a *signal* node that may be viewed as a folder containing signals
 - a *sync* node, in charge of the synchronization messages
 - a *javascript* node, that may be addressed to run javascript code dynamically.


Each component includes a static node named *debug* that provides debugging information.

- **the signals level** contains signals i.e. objects that accept data streams and that may be graphically rendered as a scene component (see Signals and Graphic signals section 15 p.56).

NOTE Since version 1.05, each component of a score may also be a container and thus, the hierarchy described above has a potential infinite depth level. Note also that a *sync* node is present at each level.

2.3 Aliases

An alias mechanism allows an arbitrary OSC address to be used in place of a real address. An *alias* message is provided to describe aliases:



- [1] sets OSCAlias as an alias of OSCAddress. The alias may be optionally followed by message strings which are then taken as implied messages. These messages can also be optionally followed by a scaling specification.
- [2] removes OSCAddress aliases.

NOTE Regular expressions are not supported by the alias mechanism and could lead to unpredictable results.

EXAMPLE

```
# makes the address /ITL/scene/myobject available using /1/fader1
/ITL/scene/myobject alias '/1/fader1';

# the following input message:
/1/fader1 0.5;
# will be translated into:
/ITL/scene/myobject 0.5;
```

```
# create an alias with an implicit 'x' message
/ITL/scene/myobject alias '/1/fader1' x;

# the following input message:
/1/fader1 0.5;
# will be translated into:
/ITL/scene/myobject x 0.5;
```

2.3.1 Scaling

In INScore, the parameter values are generally in the range [-1, 1]. However, some devices can generate messages with their own values range (e. g. accelerometers). An optional scaling string allows to convert any input range into the [-1, 1] range.

The general form of the scaling string is [n,m], where *n* and *m* are 2 numbers describing the minimum and maximum input values. Any input value *v* is then transformed into a value *v'* such that:

$$v' = 2(v - n) / (m - n) - 1$$

EXAMPLE

```
# create an alias with an implicit 'x' message using a scaling specification
/ITL/scene/myobject alias '/1/fader1' x[0,100];

# the following input message:
/1/fader1 5;
# will be translated into:
/ITL/scene/myobject x -0.9;
```

2.3.2 Using more than one implicit message

You can use an arbitrary number of message strings in an alias message. In any case, an input message with the corresponding values is expected. For example, when the alias message has 3 messages strings, input messages

are expected to have 3 associated values. These values are distributed in sequence with each message string, which also means that the input message is translated into 3 different messages.

EXAMPLE

```
# create an alias with implicit 'x' 'y' and 'angle' messages using scaling
/ITL/scene/myobject alias '/1/fader1' x[0,100] y[0,100] angle;


# the following input message:
/1/fader1 5 60 12;
# will be translated into:
/ITL/scene/myobject x -0.9;
/ITL/scene/myobject y 0.2;
/ITL/scene/myobject angle 12;
```

Chapter 3

Common messages

Common messages are intended to control the graphic and the time space of the components of a scene. They could be sent to any address with the form `/ITL/scene` or `/ITL/scene/identifier` where *identifier* is the unique identifier of a scene component.

commonMsg



- `show`: shows or hides the destination object. The parameter is interpreted as a boolean value. Default value is 1.
- `del`: deletes the destination object.
- `lock`: if not null, cancel any `del` message sent to this object. However, the object will still be deleted if one of its parents receives a `del` message. The parameter is interpreted as a boolean value. Default value is 0.
- `export` and `exportAll`: exports an object to an image file respectively without or with its childrens. If the exported object is a scene, childrens are always exported.
 - 1) exports to the `filePath` name. The `filePath` can be relative or absolute. When the filename is not

specified, exports to `path/identifier.pdf`. The file extension is used to infer the export format. Supported extensions and formats are: *pdf, bmp, gif, jpeg, png, pgm, ppm, tiff, xbm, xpm*.

2) exports to `rootPath/identifier.pdf`.

When the destination file is not completely specified (second form or missing extension), there is an automatic numbering of output names when the destination file already exists.

- `save`: recursively saves objects states to a file. When a `message` list is present, only the specified attributes are saved. The `filePath` can be relative or absolute. When relative, an absolute path is build using the current `rootPath` (see application or scene current paths p.37 and p.42). The optional `+` parameter indicates an append mode for the write operation. The message must be sent to the address `/ITL` to save the whole application state.
- `'PositionMsg'` are absolute and relative position messages.
- `'ColorMsg'` are absolute and relative color control messages.
- `'TimeMsg'` are time management messages. They are described in section 4 p.17.
- `'WatchMsg'` are described in section 17 p.68.
- `'EventMsg'` are described in section 17.4 p.73.

EXAMPLE

Export of a scene to a given file as jpeg at the current root path:

```
/ITL/scene export 'myexport.jpg';
```

Saving a scene to `myScore.inscore` at the current root path, the second form saves only the `x`, `y` and `z` attributes, the third form uses the append mode:

```
/ITL/scene save 'myScore.inscore';
/ITL/scene save x y z 'thePositions.inscore';
/ITL/scene save 'myScore.inscore' '+';
```

Hiding an object:


```
/ITL/scene/myObject show 0;
```

NOTE

when a list of attributes is specified, unknown attributes are silently ignored.

3.1 Positioning


PositionMsg



Graphic position messages are absolute position or relative position messages. They can also control an object *origin* and transformations like rotation around an axis.

3.1.1 Absolute positioning

absPosMsg



- **x y:** moves the *x* or *y* coordinate of a component. By default, components are centered on their *x*, *y* coordinates. The coordinates space range is $[-1, 1]$.
For a scene component, -1 is the leftmost or topmost position, 1 is the rightmost or bottommost position. $[0, 0]$ represents the center of the scene.
For the scene itself, it moves the window in the screen space and the coordinate space is orthonormal, based on the screen lowest dimension (*i.e.* with a 4:3 screen, $y=-1$ and $y=1$ are respectively the exact top and bottom of the screen, but neither $x=-1$ nor $x=1$ are the exact left and right of the screen).
Default coordinates are $[0, 0]$.
- **z:** sets the *z* order of a component. *z* order is actually relative to the *scene* components: objects of high *z* order will be drawn on top of components with a lower *z* order. Components sharing the same *z* order will be drawn in an undefined order, although the order will stay the same for as long as they live.
Default *z* order is 0.
- **angle:** sets the *angle* value of a component, which is used to rotate it around its center. The angle is measured in clockwise degrees from the *x* axis.
Default angle value is 0.
- **scale:** reduce/enlarge a component. Default scale is 1.


EXAMPLE

Moving and scaling an object:

```
/ITL/scene/myObject x -0.9;
/ITL/scene/myObject y 0.9;
/ITL/scene/myObject scale 2.0;
```

3.1.2 Relative positioning

relPosMsg



- **dx, dy, dz** messages are similar to *x*, *y*, *z* but the parameters represent a displacement relative to the current target value.

- `drotatex`, `drotatey`, `drotatez` are relative rotation messages. `dangle` is equivalent to `drotatez` and is maintained only for compatibility reasons.
- `dscale` is similar to `scale` but the parameters represents a scale multiplying factor.

EXAMPLE


Relative displacement of an object:

```
/ITL/scene/myObject dx 0.1;
```

3.1.3 Components origin

The origin of a component is the point (x_o, y_o) such that the (x, y) coordinates and the (x_o, y_o) point coincide graphically. For example, when the origin is the top left corner, the component top left corner is drawn at the (x, y) coordinates.

originMsg



- `xorigin`, `yorigin` are relative to the component coordinates space i.e. $[-1, 1]$, where -1 is the top or left border and 1 is the bottom or right border. The default origin is $[0, 0]$ i.e. the component is centered on its (x, y) coordinates.
- `dxorigin`, `dyorigin` represents displacement of the current `xorigin` or `yorigin`.

EXAMPLE


Setting an object graphic origin to the top left corner.

```
/ITL/scene/myObject xorigin -1. ;
/ITL/scene/myObject yorigin -1. ;
```

3.2 Components transformations

A component transformation specifies 2D transformations of its coordinate system. It includes shear and object rotation on x, y and z axis.

transformMsg



- `rotatex rotatex rotatex`: rotates the component around the corresponding axis. Parameter value expresses the rotation in degrees.
- `drotatex drotatex drotatex`: relative rotations.
- `shear` transforms the component in x and y dimensions. x and y are float values expressing the transformation value in the corresponding dimension. Values should be in the range]-1, 1[.
- `dshear` relative shear transformation.

EXAMPLE


Rotating an object graphic on the z axis.

```
/ITL/scene/myObject rotatez 90. ;
```

NOTE `angle` and `rotatez` are equivalent. `angle` has been introduced before the transformation messages and is maintained for compatibility reasons.

3.3 Color messages


ColorMsg



Color messages are absolute or relative color control messages. Color may be expressed in RGBA or HSBA or using a color name.


3.3.1 Absolute color messages

absColorMsg



red, green, blue, hue, saturation, brightness, alpha messages address a specific part of a color using the RGB or HSB scheme.

colorvalue



The value may be specified as integer or float. The data range is given in table 3.1. When the alpha component is not specified, the color is assumed to be opaque.

Component	integer range	float range
red [R]	[0,255]	[-1,1]
green [G]	[0,255]	[-1,1]
blue [B]	[0,255]	[-1,1]
alpha [A]	[0,255]	[-1,1]
hue [H]	[0,360]	[-1,1] mapped to [-180,180]
saturation [S]	[0,100]	[-1,1]
brightness [B]	[0,100]	[-1,1]


Table 3.1: Color components data ranges when expressed as integer or float.

EXAMPLE

The same alpha channel specified as integer value or as floating point value:

```
/ITL/scene/myObject alpha 51 ;
/ITL/scene/myObject alpha 0.2 ;
```

3.3.2 The color messages




`color` sets an object color in the RGBA space. The color can be specified in different ways:

- **1** sets the color using RGB values. Alpha is not specified and the color is assumed to be opaque.
- **2** sets the color using RGBA values.
- **3** sets the color using a name among html defined names (see at https://www.w3schools.com/colors/colors_names.asp). Name is not case sensitive.
- **4** sets the color using a single hexadecimal value in the form `0xrrggbb` or `0xrrggbbaa`.

The default color value is `[0,0,0,255]`.


3.3.3 The hsb messages



`hsb` sets an object color in the HSBA space. When A is not specified, the color is assumed to be opaque.

3.3.4 Relative color messages

relColorMsg



- dred, dgreen, etc. messages are similar to red, green, etc. messages but the parameters values represent a displacement of the current target value.
- dcolor and dhsb are similar and each color parameter represents a displacement of the corresponding target value.

EXAMPLE

Moving a color in the RGBA space:

```
TL/scene/myObject dcolor 10 5 0 -10 ,
```

will increase the red component by 10, the blue component by 5, and decrease the transparency by 10.


NOTE Objects that are carrying color information (images, SVG) don't respond to color change but are sensitive to transparency changes.

3.4 Pen control

Pen messages accepted by all the components and result in 2 different behaviors:

- for components types rect | ellipse | polygon | curve | line | graph | fast graph | grid, it makes the object border visible using the pen attributes;
- for the other components and when the pen width is greater than 0, it makes the object bounding box visible.


penMsg



- penWidth controls the pen width. The default value is 0 (excepted for line objects, where 1.0 is the default value). It is expressed in arbitrary units (1 is a reasonable value).

- `penColor` controls the pen color. The color should be given in the RGBA space. The default value is opaque black (0 0 0 255).
- `penStyle` controls the pen style.
- `penAlpha`, `penAlpha` controls the pen transparency only. See section 3.3.2 p.12 for the expected

penstyle



The pen style default value is `solid`.

EXAMPLE

Setting a rectangle border width and color:


```

/ITL/scene/rect set rect 0.5 0.5 ;
/ITL/scene/rect penWidth 2. ;
/ITL/scene/rect penColor 255 0 0 ;
  
```

3.5 The 'effect' messages

The effect message sets a graphic effect on the target object.

effectMsg




- `none`: removes any effect set on the target object.
- `blur`, `colorize`, `shadow`: sets the corresponding effect. An effect always replaces any previous effect. The effect name is followed by optional specific effects parameters.


NOTE An effect affects the target object but also all the target slaves.

3.5.1 The blur effect

blurParams



Blur parameters are the blur radius and a rendering hint. The radius is an `int32` value. By default, it is 5 pixels. The radius is given in device coordinates, meaning it is unaffected by scale.


blurHint

Use the `performance` hint to say that you want a faster blur, the `quality` hint to say that you prefer a higher quality blur, or the `animation` when you want to animate the blur radius. The default hint value is `performance`.

EXAMPLE

Setting a 8 pixels effect on `myObject`

```
/ITL/scene/myObject effect blur 8;
```

3.5.2 The colorize effect*colorizeParams*


Colorize parameters are a strength and a tint color. The strength is a float value. By default, it is 1.0. A strength 0.0 equals to no effect, while 1.0 means full colorization.

The color is given as a RGB triplet (see section 3.3.2 p.12) by default, the color value is light blue (0, 0, 192).

EXAMPLE

Setting a red colorize effect on `myObject` with a 0.5 strength.

```
/ITL/scene/myObject effect colorize 0.5 200 0 0;
```

3.5.3 The shadow effect*shadowParams*

`xoffset` and `yoffset` are the shadow offset and should be given as `int32` values. The default value is 8 pixels. The offset is given in device coordinates, which means it is unaffected by scale.

The color is given as a RGBA color (see section 3.3.2 p.12) by default, the color value is a semi-transparent dark gray (63, 63, 63, 180)

The blur radius should be given as an `int32` value. By default, the blur radius is 1 pixel.

EXAMPLE


Setting a shadow effect on `myObject`.

The shadow offset is (10,10) pixels, the color is a transparent grey (100,100,100, 50) and the blur is 8 pixels.

```
/ITL/scene/myObject effect shadow 10 10 100 100 100 50 8;
```

3.6 The 'edit' message

The `edit` message opens a small editor that allows to edit the target object attributes.



- **1:** without argument, the editor is initialized with all the target object attributes.
- **2:** using a list of attributes, the editor is initialized with the target object corresponding attributes. Note that `set` as attribute can be used to edit the object `set` message.
- **3:** `reset` is used to clear the edit string stored in the object cache. It is equivalent to the 'clear' button in the edit dialog. Note that as long as the edit string stored in the cache is not empty, `edit` messages are ignored unless followed by a `reset` (see below).

Each object maintains the current content of the editor, that is initialized at first `edit` message or when this content is cleared. Successive call to `edit` will preserve the editor content unless it is cleared.

NOTE Since the editor preserves its content, it doesn't take account of changes that may result from received messages and thus may not reflect the target object changes. To synchronize the editor content with the current attributes values, you can clear the editor content, which will refresh the attributes to their current values.

NOTE Although initialized with the target object attributes, the editor supports arbitrary INScore messages, i.e. addressed to any other object or even making use of extended OSC addresses.

EXAMPLE

Editing an object on double click:

```
/ITL/scene/myObject watch doubleClick (/ITL/scene/myObject edit);
```

Editing some specific attributes:

```
/ITL/scene/myObject watch doubleClick (/ITL/scene/myObject edit x y);
```


Chapter 4

Time management messages


4.1 Date and duration

Time messages control the time dimension of the score components. They could be sent to any address with the form `/ITL/scene/identifier` where *identifier* is the unique identifier string of a scene component.

timeMsg



time



- 1) Time is specified as a rational value d/n where $1/1$ represents a whole note.
 - 2) Time may be specified with a single integer, then 1 is used as implicit denominator value.
 - 3) Time may be specified as a single float value that is converted using the following approximation: let f be the floating point date, the corresponding rational date is computed as $f \times 10000 / 10000$.
 - 4) Time may also be specified as a string in the form ' n/d '.
-
- `clock`: similar to MIDI clock message: advances the object date by $1/24$ of quarter note.
 - `durClock`: a clock message applied to duration: increases the object duration by $1/24$ of quarter note.
 - `date`: sets the time position of an object. Default value is $0/1$.
 - `duration`: changes the object duration. Default value is $1/1$.
 - `ddate`: relative time positioning message: adds the specified value to the object date.
 - `dduration`: relative duration message: adds the specified value to the object duration.

EXAMPLE

Various ways to set an object date.

```
/ITL/scene/myObject date 2 1 ;  
/ITL/scene/myObject date 2;      # the denominator is 1 (implied)  
/ITL/scene/myObject date 0.5;    # equivalent to 1/2  
/ITL/scene/myObject date '1/2';  # the string form
```


Similar ways to move an object date.

```
/ITL/scene/myObject clock;  
/ITL/scene/myObject ddate '1/96';
```

4.2 Tempo

The tempo message is supported by all the score components. Its default value is 0. When non null, the date of an object is moved at the corresponding tempo (e.g. with a tempo = 60, the date move will be 1/4 - a quarter note - every second). Note that the date is refreshed at INScore time task rate.

tempoMsg



- tempo: set an object tempo. Default value is 0.
- dtempo: relative tempo message: adds the specified value to the object tempo.

EXAMPLE

A cursor moving over a score using the tempo message.


```
/ITL/scene/score set gmn "[a a a a a]";    #a short score  
/ITL/scene/cursor set ellipse 0.5 0.5;    #a cursor  
/ITL/scene/sync cursor score;              #synchronizes the cursor to the score  
/ITL/scene/cursor tempo 80;                #an set the tempo
```


Chapter 5

Miscellaneous messages

The following messages are supported by all the objects. They are detailed in specific sections.

miscMsgs




- **eval**: evaluates a list of messages in the context of the receiver object. The messages can use *relative OSC addresses* i.e. addresses that start with a dot ('.'). In this case, the leading '.' is replaced by the receiver OSC address.
- **watch**: used to manage the object interaction with various events. See section 17 p.68 for more details.
- **push, pop**: saves and restores the object interaction state. See section 17.6 p.76 for more details.
- **map**: used to describe the relations between graphic and time spaces. See section 13 p.49 for more details.

Chapter 6

The 'set' message

The `set` messages can be sent to any address with the form `/ITL/scene/identifier`. The global form of the message is:

setMsg



It sets a `scene` component data.


When there is no destination for the OSC address, the component is first created before being given the message.

When the target destination type doesn't correspond to the message `type`, the object is replaced by an adequate object.

6.1 Symbolic music notation

Symbolic music notation support is based on the Guido Music Notation format [GMN] or on the MusicXML format. MusicXML is supported via conversion to the GMN format when the MusicXML library is present.

setScore



- `gmn`: a Guido score defined by a GMN string.
- `gmnf`: a Guido score defined by a GMN file.
- `gmstream`: a Guido score defined by a GMN stream (a GMN string that can be written in several times).
- `musicxml`: a score defined by a MusicXML string.
- `musicxmlf`: a score defined by a MusicXML file.
- `gmn expr`: a score defined by a *score expression*. See section 18 p.78 for the score expressions reference.

EXAMPLE

Creating a music score using a Guido Music Notation language string.

```
/ITL/scene/myObject set gmn "[ a b g ]";
```

Creating the same music score as a stream.

```
/ITL/scene/myObject set gmnstream "[ a";
/ITL/scene/myObject write "b";
/ITL/scene/myObject write "g";
```


NOTE For compatibility with previous versions, passing a MusicXML string to a `gmn` object or a MusicXML file to a `gmnf` object may succeed since the system tries to parse the content as GMN content or as MusicXML content when the former fails.

NOTE Conversion from MusicXML to GMN could be achieved manually using a command line tool that is distributed with the MusicXML library (see at <https://github.com/dfober/libmusicxml>). It allows to improve the output GMN code afterward.

6.2 Piano roll music notation

Piano roll music notation is based on the Guido Music Notation format [GMN].

setPianoRoll



- `pianoroll`: a piano roll defined by a GMN string.
- `pianorollstream`: a piano roll defined by a GMN stream (a GMN string that can be written in several times).
- `pianorollf`: a piano roll defined by a guido file (with ".gmn" extension) or by a midi file (with ".mid" extension). Warning: url forms are not supported for midi files.
- `pianoroll expr`: a piano roll defined by a *score expression*. See section 18 p.78 for the score expressions reference.

EXAMPLE

Creating a pianoroll using a Guido Music Notation language string.


```
/ITL/scene/myObject set pianoroll "[ a b g ]";
```

Creating the same piano roll as a stream.

```
/ITL/scene/myObject set pianorollstream "[ a";
/ITL/scene/myObject write "b";
/ITL/scene/myObject write "g";
```

6.3 Textual components


setText



- `txt`: a textual component.
- `txtf`: a textual component defined by a file.
- `html`: an html component defined by an HTML string.
- `htmlf`: an html component defined by an HTML file.

Text may be specified by a single quoted string or using an arbitrary count of parameters that are converted to a single string with a space used as separator.

txtStream



EXAMPLE

Creating a text object.


```
/ITL/scene/myObject set txt "Hello ... world!";
```

Setting the content of a text object using a values stream.

```
/ITL/scene/myObject set txt Hello 1 world and 0.5;
```

6.4 Vectorial graphics

setVGraphics



- `svg`: SVG graphics defined by a SVG string.
- `svgf`: vectorial graphics defined by a SVG file.
- `rect`: a rectangle specified by a width and height. Width and height are expressed in scene coordinates space, thus a width or a height of 2 corresponds to the width or a height of the scene.
- `ellipse`: an ellipse specified by a width and height.

- **polygon**: a polygon specified by a sequence of points, each point being defined by its (x,y) coordinates. The coordinates are expressed in the `scene` coordinate space, but only the relative position of the points is taken into account (*i.e* a polygon A = { (0,0) ; (1,1) ; (0,1) } is equivalent to a polygon B = { (1,1) ; (2,2) ; (1,2) }).
- **curve**: a sequence of 4-points bezier cubic curve. If the end-point of a curve doesn't match the start-point of the following one, the curves are linked by a straight line. The first curve follows the last curve. The inner space defined by the sequence of curves is filled, using the object color. The points coordinates are handled like in a polygon.
- **arc**: an arc defined by its enclosing rectangle and the start and end angles. Angles are in degrees and express counter-clockwise directions.
- **line**: a simple line specified by a point (x,y) expressed in `scene` coordinate space or by a width and angle. The point form is used to compute a line from (0,0) to (x,y), which is next drawn centered on the scene.

EXAMPLE

Creating a rectangle with a 0.5 width and a 1.5 height.

```
/ITL/scene/myObject set rect 0.5 1.5;
```

Creating a line specified using width and angle.

```
/ITL/scene/myObject set line wa 1. 45.;
```


6.5 Signals and graphic signals

Signals are special objects that are stored in a special `signal` node and that may be composed in parallel to produce graphic signals. Signals and graphic signals are described in section 15 p.56.

Signals and computation on signals may be based on FAUST objects that are actually signals processors. FAUST objects are described in section 19.1 p.82.

For more information about the FAUST language, see at <http://faust.grame.fr>.

setGraphicSignal




- **graph**: graphic of a signal. See section 15 p.56 for details about the `graph` objects data.
- **fastgraph**: fast rendering graphic signal. See also section 15 p.56.
- **faust**: a FAUST object as a plugin (see section 19.1)
- **faustdsp**: a FAUST object defined by a string (see section 19.1 p.82)
- **faustdspf**: a FAUST object defined by a file (see section 19.1 p.82)

6.6 Media files

Images, video and audio are supported using various formats. See section 6.9 p.25 for more details on the supported formats.

setMedia



- **img**: an image file. The image format is inferred from the file extension.
- **memimg**: a memory capture of the object given as argument. **objectPath** indicates the target object that is captured with all its childrens. It may be an object name or a path to an object. Simple object names and relative path are looked for in the receiver layer.
- **video**: a video file. The video format is inferred from the file extension. Note that navigation through the video is made using its date.
- **audio**: an audio file. The audio format is inferred from the file extension. **audio** objects appear as a waveform but this waveform is not (yet) computed from the audio data but randomly generated.

EXAMPLE

Creating an image.

```
/ITL/scene/myObject set img "myImage.png";
```

Creating a memory image of a scene.

```
/ITL/scene/myObject set memimg "/ITL/scene";
```

NOTE


It is necessary to have an object or scene graphically rendered before a capture can be made. Since the actual graphic rendering is made asynchronously to the model update, a sequence of messages like the following:

```
/ITL/scene/myObject set gmn "[a f g]";
/ITL/scene/capture set memimg myObject;
```

won't work if the messages are handled by the same time task. A delay is necessary between the two messages. To make sure all the objects have been rendered, you can use the scene `endPaint` event.

6.7 Miscellaneous

setMisc



- **layer**: a graphic layer, may be viewed as a container (see section 12 p.48).
- **grid**: a white transparent object that provides a predefined time to graphic mapping (see section 8.9 p.34 for more details and section 13 p.49 for time to graphic relations). The parameters are **int32** values representing the number of columns and rows.

6.8 File based resources

Most of the types can be either expressed with the corresponding data, or by a path to a file containing the data. For the latter form, the object type is generally suffixed with an 'f' (e.g. `txtf`, `htmlf`, `gmnf`, `musicxmlf`, `svgf`, `faustf`). The **img**, **audio** and **video** types have only a file form (and no 'f' suffix).

A file path can be expressed as a Unix path (absolute or relative - see the scene or application `rootPath` message for relative paths handling), but also as an URL. Only the `http` protocol is currently supported.

When the system encounters an URL, it creates an intermediate object that is in charge of retrieving the corresponding data. This object has a specific `url` type that takes the target type and an url as arguments. It has a graphic appearance (actually a light gray box containing the object name and the target url) that can be controled like for any regular object.

urlType



The `url` intermediate object acts as a proxy for the target object and will transfer all its properties once the data are ready. A client can thus interact transparently with the target adress, whatever the status of the download request.

EXAMPLE

Creating a score using an URL:


```

/ITL/scene/score set gmnf "http://anyhost.adomain.org/score.gmn";
# is equivalent to
/ITL/scene/score set url gmnf "http://anyhost.adomain.org/score.gmn";
    
```

NOTE The `url` object handles specific events : `success`, `error` and `cancel` (see the section 17.1.6 p.71).

6.9 The file type

setFile



- `file`: a generic type to handle file based objects. Actually, the `file` type is translated into a one of the `txtf`, `gmnf`, `img`, `audio` or `video` types, according to the file extension (see table 6.1).

See also: the application `rootPath` message (section 9 p.37) for file based objects.

Table 6.1: File extensions supported by the `file` translation scheme.

file extension	translated type
.txt .text	txtf
.htm .html	htmlf
.gmn	gmnf
.xml	musicxmlf
.svg	svgf
.jpg .jpeg .png .gif .bmp .tiff	img
.avi .wmv .mpg .mpeg .mp4 .mov .vob	video
.mp3 .wav .aiff .aif, .m4a, .aac	audio
.dsp	faustdspf

EXAMPLE

Creating an image using the `file` type.

```

/ITL/scene/myObject set file "myImage.png";
# is equivalent to
/ITL/scene/myObject set img "myImage.png";
    
```


6.10 Web objects

A score can make its content available to the Internet using specific components that provide an image of the scene over `http` or `websocket` protocols.

The `httpd` server depends on the `Httpd` server plugin and is described in section 19.3 p.87.

The `websocket` server provides a two-ways communication between INScore and distant clients. The server sends notifications to client using a `Screen updated` text message when the scene is updated. Clients can request an image by sending a `getImage` text message to the server. The server responds with a image of the scene in png format, using a `Blob` type javascript object.

webobject



- `port`: a port number for the socket communication.
- `frequency`: a minimum time in millisecond between two `Screen updated` notifications.

NOTE

A busy port prevents the server to start. The server status can be checked with the `get status` message.

EXAMPLE

Creating an `websocket` server using the port 1234 and limiting the notifications rate to one per 500 milliseconds.

```
/ITL/scene/myObject set websocket 1234 500;
```


See also: the `http` web server plugin (section 19.3 p.87).

Chapter 7

The 'get' messages

The `get` messages can be sent to any valid OSC address. It is intended to query the system state. It is the counterpart of all the messages modifying this state. The result of the query is sent to the OSC output port with the exact syntax of the counterpart message. The global form of the message is:

getMsg



The `get` message without parameter is the counterpart of the `set` message. When addressed to a container (the application `/ITL`, a scene `/ITL/scene`, the signal node `/ITL/scene/signal`) is also distributed to all the container components.

Specific `get` forms may be available, depending on the component type (see sections 8.3, 9.4, 9.5.2, 14, 15.1.2, 19.1.2).

The `get frame` message is supported by all the components. An object frame is available for read only. It represents the polygon that encloses the object, taking account of scaling, rotations, and shear. The polygon is returned as a set of 4 points (x, y) expressed in the parent object coordinates space.

EXAMPLE

Sending the following request to an object which position is 0.3 0.5

```
/ITL/scene/myobject get x y;
```

will give the following messages on output port:

```
/ITL/scene/myobject x 0.3;
```

```
/ITL/scene/myobject y 0.5;
```

Querying an object content

```
/ITL/scene/myobject get;
```

will give the corresponding `set` message:

```
/ITL/scene/myobject set txt "Hello world!";
```

Querying an object frame

```
/ITL/scene/myobject get frame;
```

will give the corresponding `frame` message:

```
/ITL/scene/myobject frame -0.5 -0.25 0.50 -0.25 0.50 0.25 -0.5 0.25;
```

NOTE

The `get width` and `get height` messages addressed to components that have no explicit width and height (text, images, etc.) returns 0 as long as the target component has not been graphically rendered.

Chapter 8

Type specific messages

Some of the messages are accepted only by specific components. This section describes the messages associated to specific objects types.

8.1 Brush control





Figure 8.1: Brush styles

`brushStyle` message is accepted by the following components:
`rect ellipse polygon curve layer.`

brushMsg

- `brushStyle` controls the brush style (see figure 8.1).

The brush style default value is `solid`.

For the `layer` object, the brush style default value is `none`.


EXAMPLE

Setting a rectangle style :

```
/ITL/scene/rect set rect 0.5 0.5 ;
/ITL/scene/rect brushStyle dense4;
```

8.2 Width and height control

`width` and `height` messages are accepted by the following components: `rect` | `ellipse` | `arc` | `graph` | `fastgraph` | `grid` | `pianoroll` | `pianorollf`.


widthMsg

NOTE Querying the `width` and `height` of any object is always supported, provided that the object has been graphically rendered.

8.3 Symbolic score

The following messages are accepted by the components types `gmn` | `gmnstream` | `gmnf`.

scoreMsg




- `page`: set the score current page
- `dpage`: moves the score current page
- `pageFormat`: set the page format. The parameters are the page width and height. Note that the message has no effect when the score already includes a `\pageformat` tag.
- `columns`: for multi pages display: set the number of columns.
- `rows`: for multi pages display: set the number of rows.
- `pageCount`: a read only attribute, gives the score pages count.
- `systemCount`: a read only attribute, gives the number of systems on each of the score pages. The result is given as a list systems count ordered by page number (index 0 is page 1, etc.).

EXAMPLE

Displaying a multi-pages score on two pages starting at page 3:

```
/ITL/scene/myScore columns 2 ;
/ITL/scene/myScore page 3 ;
```

gmnstreamMsg



- `write`: add the gmn code to the current gmn stream
- `clear`: reinitialize the stream


EXAMPLE

Writing a score in 3 steps:

```
/ITL/scene/myScore set gmnstream "[ c";
/ITL/scene/myScore write " d e";
/ITL/scene/myScore write " f]";
```

8.4 Piano roll

The following messages are accepted by the components types `pianoroll` | `pianorollstream` | `pianorollf`.

pianorollMsg

- **keyboard:** display the keyboard on left of piano roll. Default value to 0.
- **autoVoicesColoration:** enable voices automatic coloration. If *voiceColor* is used for a voice, automatic voices coloration do nothing for it. Default value to 0.
- **measureBars:** Display measure bars on piano roll. Default value to 0.
- **voiceColor:** set a color to a voice. The parameters are voice number (start to 1), and RGBA color (See section 3.3.2 p.12). If not color is present, voice color is reset to default color. If voice number and color are not present, reset all voices to default color.
- **pitchLines:** Display pitch lines on pianoroll. Parameters are a note list in english notation (A A# B ...) with case insensitive. Default to all lines. An 'empty' note (i.e. the literal 'empty' string) can be used to hide all lines.
- **clipTime:** set time limits for piano roll (See section 4 p.17 to set a time). The two times have to be wrote in the same format. If no time is present, time limits are reset to default.
- **clipPitch:** Set pitch limits to piano roll. The pitch is in midi format. If no value is present, pitch limits are reset to default.

EXAMPLE


Set a color on voice 2 with transparency and display C and F pitch lines:

```
/ITL/scene/myPianoroll voiceColor 2 154 234 45 100;
/ITL/scene/myPianoroll pitchLines 'C' 'F';
```

Removes the pitch lines:

```
/ITL/scene/myPianoroll pitchLines empty;
```

Piano roll streams support the same messages than Guido streams:

pianorollstreamMsg

- **write:** add the gmncode to the current gmncode stream

- `clear`: reinitialize the stream

EXAMPLE


Writing a pianoroll in 3 steps:

```
/ITL/scene/myPianoroll set pianorollstream "[ c";
/ITL/scene/myPianoroll write " d e";
/ITL/scene/myPianoroll write " f]";
```

8.5 Audio and Video

Media objects (audio video) have their own internal time and duration that is independent from the INScore time and duration. This time is controlled using specific messages.

media




- `play` start or stop playing the media. Default value is 0.
- `volume` sets the audio volume. Default and maximum value is 1.
- `rate` sets the media playing rate. Default value is 1.
- `vdate` sets the current video frame or audio position. Default value is 0. Arguments are the following:
 - 1): a value in milliseconds.
 - 2): a musical time expressed as a rational. Note that musical time is converted to milliseconds using a tempo value of 60.
 - 3): a musical time expressed as a float.

A media position may be updated while the media is playing.

Media objects support also specific queries:

mediaGet



- `mls` gives the media absolute duration in milliseconds.
- `vduration` gives the media duration in musical time. The returned value is a rational computed using the current rate, according to a tempo value of 60.

A media object supports specific events (see section 17.1.8 p.72 for more details).

EXAMPLE

Playing a video at half speed:

```
/ITL/scene/video set video "Video.mp4";
/ITL/scene/video rate 0.5;
/ITL/scene/video play 1";
```

NOTE


Depending on the video encoding and on the platform renderer, setting the video current position using the `vdate` message may be aligned to key frames.

Supported audio and video formats are highly dependent on the platform, as well as media specific features (e.g. setting the playing rate that may or may not be supported, or may behave differently).

8.6 SVG Objects

The following message is accepted by the SVG components (types `svg` | `svgf`).

svgMsg



- `animate`: start or stop the svg animation (provided the SVG is animated). The parameter is a boolean value (default is 0).
- `animated`: a `get` parameter only: returns whether the svg is animated or not.


NOTE

SVG objects are rendered using the Qt SVG Renderer and suffer the Qt limitations. For example and with Qt 5.5, `xlinks` are not supported.

8.7 Rectangles

Rectangles (type `rect`) accept a `radius` message that can be used to draw rounded rectangles.

radiusMsg




- `radius`: followed by 2 values that specify the radius on the x and y axis (default is 0 0). The values express a percentage of the object dimensions, thus the value's range is [0, 100].

8.8 Arcs

Arcs are portions of ellipses. Although an arc is specified by its `set` message, it supports additional messages to control the start angles and the arc extension individually. An additional `close` message affects the drawing of the arc.

arcMsg



- `start`: set the start angle of the arc.
- `range`: set the arc extension in degrees counter-clockwise.


- `dstart`: move the start angle of the arc from the value given as parameter.
- `drange`: move the arc range from the value given as parameter.
- `close`: by default, only the curve of an arc is drawn. When the `close` attribute is set, lines from the arc borders to the center of the ellipse are also drawn. The `close` parameter is read as a boolean value.

Angles are in degrees and express counter-clockwise directions.

8.9 The 'grid' object

The `grid` object provides a pre-defined time to graphic mapping organized in columns and row. By default, it is not visible (white, transparent) but supports all the attributes of rectangles (color, pen, effects, etc.). Each element of a grid has a duration that is computed as the grid duration divided by the total number of elements (columns x rows) and is placed in the time space from the date 0 to the end of the grid duration.

gridMsg



- `columns` set the number of columns of the grid,
- `rows` set the number of rows of the grid,
- `xborder` set the horizontal spacing between the elements of the grid (default is 0.),
- `yborder` set the vertical spacing between the elements of the grid (default is 0.),
- `order` defines the time order of the elements. By default, elements are organized from left to right first and from top to bottom next (`leftright`). The `topbottom` parameter changes this order from top to bottom first and from left to right next.

EXAMPLE

Creating a 10 x 10 grid organized from top to bottom with a border:

```

/ITL/scene/grid set grid 10 10 ;
/ITL/scene/grid xborder 3. ;
/ITL/scene/grid yborder 3. ;
/ITL/scene/grid order topbottom ;

```


8.10 Arrows

Specific arrows message is accepted by the component type `line`. It add capability to draw arrow heads to the begining and the end of a line object.

arrowsheadMsg



- `arrowStyleBegin` Set the arrow head of the begining of the line.
- `arrowStyleEnd` Set the arrow head of the end of the line.




arrowStyle

The arrow style default value is none.

8.11 Textual objects

8.11.1 Font control

Specific font messages are accepted by `txt` `html` `txtf` and `htmlf` components.

fontMsg*fontStyle**fontWeight*

- `fontSize` controls the font size in pixel. The default value is 13px.
- `fontFamily` controls the font family. The default value is 'Arial'. If a non existing value is used, system default font is used.
- `fontStyle` controls the pen style. The font style default value is normal.
- `weightValue` controls the font weight. The font weight default value is normal.

EXAMPLE

Setting a text object with a font family Times and bold weight:


```

/ITL/scene/text set txt "text sample";
/ITL/scene/text fontFamily Times;
/ITL/scene/text fontWeight bold;
  
```

8.11.2 Writing

Textual objects support writing in a stream-like way.

txtwrite



- **write**: append the **arg** list formatted as a string to the textual content.


EXAMPLE

```
/ITL/scene/text set txt "Hello";  
/ITL/scene/text write "world!";
```

8.12 The 'debug' nodes

Each component includes a static **debug** nodes provided to give information about components.

debugMsg



- **map** is used to display the time to graphic mapping. The parameter is a **int** value: 0 prevents mapping display, 1 displays only the bounding boxes and 2 displays also the dates along with the boxes. Default is 0 (no map).
- **name** is used to display both the object name and bounding box. The parameter is a **boolean** value. Default is 0.


Chapter 9

Application messages

Application messages are accepted by the static OSC address /ITL.

9.1 Application management

ITLMsg



- quit: requests the client application to quit.
- rootPath: *rootPath* of an INScore application is the default path where the application reads or writes a file when a relative path is used for this file. The default value is the user home directory. Sending the rootPath message without parameter resets the application path to its default value.
- preprocess: evaluates the input file script and print the result to the log window.
- mouse: hide or show the mouse pointer.

- **defaultShow**: changes the default show status for new objects.
The default defaultShow value is 1.
- **load**: loads a file previously saved using the **save** message (see section 3 p.7). Note that the load operation appends the new objects to the existing scene. When necessary, it is the sender responsibility to clear the scene before loading a file. URL are supported for the file path (see section 6.8 p.24);
- **read**: read a buffer that is expected to contain a valid inscore script.
- **require**: check that the current INScore version number is equal or greater to the number given as argument. The version number is given as a float value. A message is associated to the **require** message, which is triggered when the check fails. See section 17 p.68 for more details.
- **compatibility**: preserve INScore previous behavior. The argument corresponds to a version number, INScore will preserve the corresponding behavior (objects scaling, default size, etc.).
- **rate**: changes the time task rate. Note that null values are ignored.
The default rate value is 10.
- **time**: sets the application current time. The time is expressed in milliseconds.
- **ticks**: sets the application current ticks count. The ticks count indicates the number of time tasks performed by the application.
- **hello**: query the host IP number. The message is intended for ITL applications discovery. Answer to the query has the following format:
IP inPort outPort errPort where IP is sent as a string and port numbers as integer values.
- **forwardingMsg**: application support message forwarding and filtering. See section ?? p.??.

EXAMPLE

when sending the message:

```
/ITL hello;
```


the application will answer with the following message:

```
/ITL 192.168.0.5 7000 7001 7003
```

when it runs on a host which IP address is 192.168.0.5 using the default port numbers.

9.2 Ports management

ITLPortsMsg



Changes the UDP port numbers:

- **port** defines the listening port number,
- **outport** defines the port used to send replies to queries,
- **errport** defines the port used to send error messages.

The **int32** parameter should be a positive value in the range [1024-49150].


The default port, outport and errport values are 7000, 7001 and 7002.

NOTE

Error messages are sent as a single string.

9.3 System support

ITLSystem




- browse open the file given as parameter using the system default browser. The message supports URLs that can be of type `http://`, `https://` or `file://`. It supports also direct reference to a local file (e.g. `myfile.html`) that is translated into `file://` url using the application `rootPath`.

9.4 Application level queries

The application supports the `get` messages for its parameters (see section 7 p.27). In addition, it provides the following messages to query version numbers.

ITLRequest



- `version`: version number request.
- `guido-version`: Guido engine version number request.
- `musicxml-version`: MusicXML and Guido converter version numbers request. Returns "not available" when the library is not found.

EXAMPLE

Querying INScore version:

```
/ITL get version;
```

will give the following as output:


```
/ITL version 1.00
```

9.5 Application static nodes

The application level provides the static nodes - `stats`, `debug`, `log` and `ssl`, available at `/ITL/stats` `/ITL/debug`, `/ITL/log` and `/ITL/ssl`.

9.5.1 The 'stats' nodes

ITLStats



- `get` gives the count of handled messages at OSC and UDP levels: the UDP count indicates the count of messages received from the network, the OSC count includes the UDP count and the messages received internally.
- `reset` resets the counters to zero. Note that querying the `stats` node increments at least the OSC the counter.

EXAMPLE


Answer to a `get` message addressed to `/ITL/stats`

```
/ITL/stats osc 15 udp 10
```

9.5.2 The 'debug' nodes

The debug node is used to activate debugging information.

ITLdebug



- switch the debug mode ON or OFF. The parameter is interpreted as a boolean value. When in debug mode, INScore sends verbose messages to the OSC error port for every message that can't be correctly handled. Debugging is ON by default.

EXAMPLE


Error messages generated on error port in debug mode:

```
error: incorrect OSC address: /ITL/stat
error: incorrect parameters: /ITL/scene/foo unknown 0.1
error: incorrect parameters: /ITL/scene/foo x "incorrectType"
```

9.5.3 The 'log' nodes

The log node controls a console window that display all the messages sent to the OSC error port. Typical content is given by the example above.

ITLLog




- **show** show or hides the console. The parameter is a boolean value.
- **clear** clear the console window.
- **foreground** put the console window to front.
- **wrap** control line wrapping of the console. The parameter is a boolean value.
- **write** write the `arg` list formatted as a string to the log window.
- **save** save the current log content to a file. The parameter is a file name. When expressed as a relative path, the file is saved under the current application root path.
- **level** set the log level. Expected values are:
 - 0 : no log
 - 1 : log errors (default value)
 - 2 : log errors and output of `get` messages
- **scale** scales the log window content. Default value is 1.0.

9.5.4 The 'plugins' nodes

The `plugins` node controls the search path for plugins. See section 19 p.82 for more information on plugins and search strategies.

ITLPlugin



- `path` add `folder` as a user path. The system will look for plugins in this folder first.
- `reset` clear the current user path.

9.5.5 The 'ssl' node

The `ssl` node is provided to manage certificates for encrypted communication with remote hosts. See section 11.2 p.46 for more details and section 11 p.45 for communication scheme.

Chapter 10


Scene messages

A scene may be viewed as a window on the score elements. Its address is `/ITL/sceneIdentifier` where *sceneIdentifier* is a user defined scene name. A scene named `scene` is created on startup.

10.1 Scene control

The following messages are available at scene level, to control the scene appearance and behaviour:

sceneMsg



- `new`: creates a new scene and opens it in a new window.
- `del`: deletes a scene and closes the corresponding window.
- `reset`: clears the scene (i.e. delete all components) and resets the scene to its default state (position, size and color).
- `foreground`: display scene window in foreground of all other windows in the system windows manager.

- `rootPath`: *rootPath* of a scene is the default path where the scene reads or writes a file when a relative path is used for this file. When no value has been specified, the application *rootPath* is used. Calling `rootPath` without argument clears the scene *rootPath*.
- `preprocess`: evaluates the input file script and print the result to the log window.
- `load`: loads an INScore file to the scene. Note that the OSC addresses are translated to the scene OSC address.
- `fullscreen`: requests the scene to switch to full screen or normal screen. The parameter is interpreted as a boolean value. Default value is 0.
- `frameless`: requests the scene to switch to frameless or normal window. The parameter is interpreted as a boolean value. Default value is 0.
- `absolutexy`: requests the scene to absolute or relative coordinates. Absolute coordinates are in pixels relative to the top left corner of the screen. Relative coordinates are in the range [-1, 1] where [0,0] is the center of the screen. The message parameter is interpreted as a boolean value. Default value is 0.
- `windowOpacity`: switch the scene window to opaque or transparent mode. When in transparent mode, the scene alpha channel controls the window opacity (from completely opaque to completely transparent). In opaque mode, the scene alpha channel controls the background brush only. Default value is 0 (transparent).
- `commonMsg`: a scene support the common graphic attributes. See section 3 p.7.
- `forwardingMsg`: a scene support message forwarding and filtering. See section ?? p.??.

EXAMPLE

Setting a scene current path:

```
/ITL/scene rootPath "/path/to/my/folder";
```

Loading an INScore file:

```
/ITL/scene load "myscript.inscore";
```

will load `/path/to/my/folder/myscript.inscore` into the scene.

Setting a scene to fullscreen:

```
/ITL/scene fullscreen 1;
```


Creating a new score named `myScore`:

```
/ITL/myScore new;
```

10.2 OpenGL rendering

A scene supports optional OpenGL rendering.

openglMsg




- `opengl`: requests the scene to switch to OpenGL or normal rendering. The parameter is interpreted as a boolean value. Default value is 0.

NOTE

OpenGL rendering improves significantly the performance of graphic operations but at the cost of dirty rendering for text and scores.

10.3 Scene queries

A scene may respond to queries regarding its elements:

sceneQuery

- **count**: count the number of elements in the scene.
- **rcount**: recursively count the number of elements in the scene.

EXAMPLE

Counting the elements in a scene:

```
/ITL/scene get count;  
    will give a message like the following as output:  
/ITL/scene count 200;
```

Chapter 11


Messages forwarding

The messages handled by the application or by a scene can be forwarded to arbitrary remote hosts. A filtering mechanism can be used to have a fine control of forwarded messages.

11.1 Remote hosts list


Remote hosts lists can be set using the `forward` message at scene or application level. Hosts lists of the application and of each scene are independent. At scene level, only messages handle by the scene are forwarded (ie message for the scene itself or for one of his children object). The `forward` message itself can't be forwarded. A message from a host cannot be forwarded to him to avoid direct loop.

ITLMsgForward



- 1) removes the set of forwarded destinations,
- 2) set a list of remote hosts for forwarding.

ForwardDest



The forwarding mechanism can use different protocols, expressed by the destination in the form of an url, optionally followed by a port number separated by a semi-colon. By default, when no port number is specified, the default application listening port number is used (7000).

- 1) obsolete form preserved for compatibility: it's equivalent to 2).
- 2) messages are forwarded using the OSC protocol.
- 3) messages are forwarded in textual form using the HTTP protocol.

- 3) messages are forwarded in textual form using the HTTPS protocol. See section 11.2 about additional requirements for encrypted connections.
- 5) messages are forwarded in textual form using WebSockets.

EXAMPLE

Forwards messages at application level to `host1.adomain.org` using OSC and the default application listening port number (7000) and to `host2.adomain.org` using HTTP on port number 5100 .


```
/ITL forward osc://host1.adomain.org http://host2.adomain.org:5100;
```

11.2 SSL support

When you use `https` as a communication protocol, a digital certificate and an encryption key are required to establish connections between INScore and the client stations. The certificate must be signed by a trusted certificate authority. Short term certificates are freely available on the internet.

Before issuing a `forward` message on an encrypted communication channel, the key and certificate must be loaded by INScore. For this purpose, a set of messages is provided by the application `ssl` node `/ITL/ssl`:

SslSetup




- `key` load 'file' as private key
- `cert` load 'file' as digital certificate
- `cacert` load 'file' as intermediate certificate used as certificate authority

file is a path to a file that can be absolute or relative. Resolution of relative paths differs from the approach used with `rootPath`: a path expressed as relative will always refer to the `.ssh` folder located at the root of the user directory (\$HOME).

11.3 Filters

The messages forwarded to arbitrary remote hosts using the `forward` message can be filtered to send only wanted messages. The static `filter` node is use manage the filter. A static `filter` node is created for each scene and one at application level. The filter can be construct with OSC address and messages.

ITLFilteringForward



- 1) Replace the current accepted list by the new list or by an empty list. Item in accepted list are not filtered by the reject item list.

- 2) Replace the current accepted list by the new list or by an empty list. Item in reject list are filtered if they not match the accept list.

When a new message is incoming, if they match to an accepted item, filter is not apply.

EXAMPLE

Filter at application level :

```
/ITL/filter reject /ITL/scene/line* /ITL/scene/rect;
/ITL/filter accept /ITL/scene/line2 scale arrows;
```

Messages with address starting with `/ITL/scene/line` or addressed to `/ITL/scene/rect` are filtered only if message address is not `/ITL/scene/line2` or if the content is not `scale` or `arrows`.

Filter at scene level :

```
/ITL/scenel/filter reject fontWeight /ITL/scenel/rect;
```

The `fontWeight` message and message for `/ITL/scenel/rect` are rejected.


NOTE

INScore is message based in a consistent way: all actions are triggered by messages (including, for example, quitting the application). Some messages are generated internally. This is the case of `ddate`: an object sends `ddate` messages to itself when its tempo is not zero. It is therefore recommended to filter `ddate`: in the absence of a filter, a recipient who receives a `tempo` message will generate these messages internally, but will also receive those that have been forwarded. Its actual tempo will then be twice the one set.

11.4 Specific queries

When using connection oriented protocols with the `forward` message (`http`, `https`, `ws`), you can query the number of connected clients:

ITLClientsQuery



The message must be addressed at the application level (`/ITL`). The answer is detailed for each type of connection-oriented protocol in service.

Chapter 12

Layers

Layers may be viewed as containers or as groups. They represent a way to structure both the address space and the graphic space.

From graphic viewpoint, a layer is a scene inside a scene. All the properties of 'rect' components are available to layers: position, scale, color, transparency, etc.). By default, a layer is not visible: it has no brush and no pen, but changing the brush style (see section 8.1 p.28) - e.g. to `solid` - makes it visible.

From time viewpoint, a layer has the common time attributes i.e. a date, a duration.

A layer may be synchronized to other objects, including other layers. It includes a `sync` node and supports synchronization of the enclosed objects. However, synchronization is restricted to objects from the same layer and cannot cross the border of a layer.

EXAMPLE

Creating a layer and its content:

```
/ITL/scene/layer1 set layer;  
/ITL/scene/layer1/score set gmnf 'myscore.gmn';  
/ITL/scene/layer1/cursor set rect 0.01 0.1;
```

Synchronizing 2 components of a layer :

```
#'score' and 'cursor' must be enclosed in layer1  
/ITL/scene/layer1/sync cursor score;
```

Making a layer visible :

```
/ITL/scene/layer1 brushStyle solid;  
/ITL/scene/layer1 color 120 120 120;
```

12.1 Layers generalization

The idea of layer is generalized to all the type of objects: any INScore object can be a container without depth limitation.

Layers but also any object respond to the `count` and `rcount` queries described in section 10.3 p.43.

Chapter 13


Mapping graphic space to time space

Time to space mapping refers to the description of relationship between an object local graphic space and its time space. A mapping consists in a set of relations between the two spaces. INScore provides specific messages to describes mappings and to synchronize arbitrary objects i.e. to display their time relationships in the graphic space.

13.1 The 'map' message


The `map` messages can be sent to any address with the form `/ITL/scene/identifier`. It is intended to describe the target object relation to time and sets a relation between an object segmentation and a time segmentation. The global form of the message is:

mapMsg



The `relation` parameter must be sent as a single string which format is described below. It consists in a list of associations between the object local space and its time space expressed as segments.

relation



Segments are expressed as a list of intervals. For a 1 dimension resource, a segment is a made of a single interval. For a 2 dimensions resource, a segment is a made of 2 intervals: an interval on the x-axis and one on the y-axis for graphic based resource, or an interval on columns and one on lines for text based resources. Intervals are right-opened.

The different kind of relations corresponds to:

- [1] a relation between a 2 dimensions segmentation expressed in float values and a relative time segmentation. These segmentations are used by `rect`, `ellipse`, `polygon`, `curve`, `line` components.
- [2] a relation between a 2 dimensions segmentation expressed in integer values and a relative time segmentation. These segmentations are used by `txt`, `txtf`, `img` components.

- [3] a relation between a 1 dimension segmentation expressed in integer values and a relative time segmentation. These segmentations are used by the `graph` component and express a relation between a signal space and time.

Table 13.1 summarizes the specific local segmentation used by each component type.

The specified `map` can be named with an optional `mapName` string; this name can be further reused, during object synchronization, to specify the mapping to use. When `mapName` is not specified, the mapping has a default *empty name*.


The `del` command deletes the mapping specified with `mapName`, or the '*empty name*' mapping if no map name is specified.

Table 13.1: Local segmentation type for each component

component type	segmentation type
txt, txtf	int2DSegments
img	int2DSegments
rect, ellipse, polygon, curve	float2DSegments
graph	int1DSegments

13.1.1 Segments definitions


timeSegment




relativeTimeSegment




absoluteTimeSegment




float2DSegment



int2DSegment



int1DSegment




relativeTimeInterval



absoluteTimeInterval



floatInterval



intInterval



Relative time is expressed as rational values where 1 represents a whole note.

rational



Absolute time is expressed in minutes, seconds and cents. It is automatically converted to relative time, assuming that the tempo is 60 quarter notes per minute.

absoluteTime



EXAMPLE

Mapping an image graphic space to time:

```
/ITL/scene/myImage map
" ( [0, 67[ [0, 86[ ) ( [0/2, 1/2[ )
  ( [67, 113[ [0, 86[ ) ( [1/2, 1/1[ )
  ( [113, 153[ [0, 86[ ) ( [1/1, 3/2[ )
  ( [153, 190[ [0, 86[ ) ( [3/2, 2/1[ )
  ( [190, 235[ [0, 86[ ) ( [2/1, 5/2[ ) " ;
```

the image is horizontally segmented into 5 different graphic segments that express pixel positions. The vertical dimension of the segments remains the same and corresponds to the interval $[0, 86[$. Each graphic segment is associated to a time interval which duration is $1/2$ (a half note).

The same mapping using absolute time assumes that 1 second is equal to 1 quarter note:

```
/ITL/scene/myImage map
" ( [0, 67[ [0, 86[ ) ( [0:0:0, 0:2:0[ )
  ( [67, 113[ [0, 86[ ) ( [0:2:0, 0:4:0[ )
  ( [113, 153[ [0, 86[ ) ( [0:4:0, 0:6:0[ )
  ( [153, 190[ [0, 86[ ) ( [0:6:0, 0:8:0[ )
  ( [190, 235[ [0, 86[ ) ( [0:8:0, 0:10:0[ ) " ;
```


NOTE ABOUT LOCAL SPACES

- Text objects (txt txtf) local space is expressed by intervals on columns and rows.
- Html object (html, htmlf) do not support mapping because there is not correspondence between the text and the graphic space.
- Vectorial objects (rect, ellipse, polygon, curve, svg, ...) express their local graphic space in internal coordinates system i.e. on the $[-1, 1]$ interval.
- Bitmap objects (img) express their local graphic space in pixels.

13.2 The 'map+' message

The map+ messages is similar to the map message but doesn't replace the existing mapping data: the specified relations are added to the existing one.


mapAddMsg



13.3 Mapping files

The `mapf` messages is similar to the `map` message but gives the path name of a file containing the mapping data, along with the optional map name.


mapfMsg



13.4 Symbolic score mappings

Mapping between the graphic and time space is automatically computed for symbolic score `gmn`, `gmnstream`, `gmnf`. However and depending on the application, the graphic space may be segmented in different ways, for instance: different graphic segments for different staves, a single graphic segment traversing all a system, etc. Thus for a symbolic score, the `map` message different and is only intended to select one king mapping supported by the system.

scoreMap



- `page`: a page level mapping
- `system`: a system level mapping
- `systemflat`: a system level mapping without system subdivision (one graphic segment per system)
- `staffn`: a staff level mapping: the staff number is indicated by `n`, a number between 1 and the score staves count.
- `voicen`: a voice level mapping: the voice number is indicated by `n`, a number between 1 and the score voices count.

The default mapping for a symbolic score is unnamed but equivalent to `staff1`.

EXAMPLE

Requesting the mapping of the third staff of a score:

```
/ITL/scene/myScore map staff3;
```

Requesting the system mapping :

```
/ITL/scene/myScore map system;
```

NOTE

A voice may be distributed on several staves and thus a staff may contain several voices.


Chapter 14

Synchronization


Synchronization between components is in charge of the static `sync` node, automatically embedded in each object. Its address is `/ITL/.../object/sync` and it supports messages to add or remove a master / slave relation between components or to query the synchronizations state.

NOTE

A master can naturally have several slaves, but a slave can have several masters as well. In this case, it will be drawn several times, corresponding to each master's space.



- [1] the `slave master` form is followed by an optional synchronization mode (see below). It adds a slave / master relation between the first and the second component.
- [2] the `slave master del` form removes the specified slave/master relation.
- [3] the `slave` form without `master` removes all synchronizations with the slave.
- [4] the `get` message is intended to query the synchronization state. The optional parameter is the identifier of a component. The `get` message without parameter is equivalent to a `get` message addressed to each object declared in the `sync` node.



Synchronization identifiers indicates

- 1) the name of an object. Note that you can use regular expressions to refer to a set of objects.
- 2) the name of an object associated to a mapping name.

Using the first form (i.e. without explicit mapping name), the system uses the default unnamed mapping (see section 13.1 p.49 mappings and named mappings).

Synchronization between components has no effect if any of the required mapping is missing (see table 13.1).

EXAMPLE

Synchronizing an object on several masters:

```
/ITL/scene/myParent/sync mySlave myMaster1;
/ITL/scene/myParent/sync mySlave myMaster2;
```

Synchronizing two objects using a specific mapping (the second object is assumed to be a symbolic score (gmn, gmnstream or gmnf) which system mapping has been previously requested):


```
/ITL/scene/myParent/sync mySlave myMaster:system;
```

14.1 Synchronization modes

Synchronizing a slave component A to a master component B has the following effect:


- A position (x) is modified to match the B time position corresponding to A date.
- depending on the optional `syncStretch` option, A width and/or height is modified to match the corresponding B dimension (see below).
- depending on the optional `syncPos` option, A vertical position (y) is modified. Note that the y position remains free and could always be modified using a `dy` message.
- if A date has no graphic correspondence in B mapping (the date is not mapped, or out of B mapping bounds), A won't be visible.

syncmode



14.1.1 Using the master date

syncHow



The synchronization mode makes use of the master time to graphic mapping to compute the slave position. It may also use the master current date, depending on the following options:

- **relative**: the time position where the slave appears is relative to the mapping AND to the master current date (actually, it shifts the mapping from the master current date). The relative mode is used by default.
- **absolute**: the time position where the slave appears corresponds to the mapping date only.

NOTE

Use of the `absolute` mode may take sense with nested synchronizations: let's consider an object A, slave of B, which is slave of C. In `relative` mode and if A and B receive the same `clock` messages, A will remain at a fixed position on B although it is moving in time.


EXAMPLE

Describing nested synchronizations, the first one using the `absolute` mode:

```
/ITL/scene/sync slave masterSlave absolute ;
/ITL/scene/sync masterSlave master ;
```

14.1.2 Synchronizing an object duration

syncStretch



The synchronization stretch mode has the following effect on the slave dimensions:

- *h*: the slave is horizontally stretched to align its begin and end dates to the corresponding master locations.
- *v*: the slave is vertically stretched to the master map vertical dimension.
- *hv*: combines the above parameters.

By default, no stretching is applied.


EXAMPLE

Synchronizing two objects, aligning the slave duration to the corresponding master space and stretching the slave to the master map vertical dimension:

```
/ITL/scene/sync mySlave myMaster hv ;
```

14.1.3 Controlling the slave position

syncPos



The synchronization position mode has the following effects on the slave *y* position:

- *syncOver*: the center of the slave is aligned to the master center.
- *syncTop*: the bottom of the slave is aligned to the top of the master.
- *syncBottom*: the top of the slave is aligned to the bottom of the master.
- *syncFrame*: used to browse the master frame (see the next section).

The default position mode is *syncOver*. The *y* attribute of the slave remains available to displacement (*dy*).

NOTE

The *y* position of a synchronized object remains a free attribute. To control this position, you should send *dy* messages.

EXAMPLE

Synchronizing two objects, aligning the slave duration to the corresponding master space, the slave being below the master map:

```
/ITL/scene/sync mySlave myMaster h syncBottom;
```

14.1.4 The syncFrame mode

When the *syncFrame* mode is used, the slave is placed on the frame of the master. Typically, this frame corresponds to the object bounding box that is also the object default mapping. For ellipses, arcs, lines, polygons, the frame corresponds to the border of the object. The frame duration is the object duration.

Mappings and stretch options are ignored in *syncFrame* mode.

Chapter 15

Signals and graphic signals

The graphic representation of a signal is approached with *graphic signals*. As illustrated in figure 15.1, the graphic representation of a signal could be viewed as a stream of a limited set of parameters : the y coordinate at a time t , a thickness h and a color c . A *graphic signal* is a composite signal including a set of 3 parallel signals that control these parameters. Thus the INScore library provides messages to create signals and to combine them into *graphic signals*.




Figure 15.1: A simple graphic signal, defined at time t by a coordinate y , a thickness h and a color c

15.1 The 'signal' static node.

A scene includes a static signal node, which OSC address is `/ITL/scene/signal` which may be viewed as a container for signals. It is also used for *composing signals in parallel*.

The signal node supports the `get` message that gives the list of the defined signals and also the `get connect` message that gives a list of all connections, but doesn't take any argument.

EXAMPLE

Querying the signal node:

```
/ITL/scene/signal get;
```

will give the enclosed signals definitions:

```
/ITL/scene/signal/y size 200 ;  
/ITL/scene/signal/h size 200 ;
```

And :


```
/ITL/scene/signal get connect;
```

will give the signal connections :

```
/ITL/scene/signal connect cos object1:method1 ;  
/ITL/scene/signal connect sin object2:method2 ;
```

15.1.1 Signal messages.

Signal messages can be sent to any address with the form `/ITL/scene/signal/identifier`, where *identifier* is a unique signal identifier. The set of messages supported by a signal is the following:



- [1] push an arbitrary data count into the signal buffer. The expected data range is $[-1, 1]$. Note that the internal data buffer is a ring buffer, thus data are wrapped when the data count is greater than the buffer size.
- [2] the `size` message sets the signal buffer size. When not specified, the buffer size value is the size of the first data message.
- [3] the `default` message sets the *default signal value*. A signal *default value* is the value returned when a query asks for data past the available values.
- [4] the `get` message without parameter gives the signal current values. The `size` and `default` parameters are used to query the signal size and default values.
- [5] the `reset` message clears the signal data.
- [6] the `del` message deletes the signal from the signal space. Note that it is safe to delete a signal even when used by a graphic signal.

EXAMPLE

Creating a signal with a given buffer size:

```
/ITL/scene/signal/mySig size 200;
```


Creating a signal with a given set of data (the buffer size will be the data size):

```
/ITL/scene/signal/mySig 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0. -0.1 -0.2 ;
```


15.1.2 Composing signals in parallel.

Composing signals in parallel produces a signal which value at a time t is a vector of the composed signals values. Thus an additional read-only attribute is defined on *parallel signals*: the signal *dimension* which is size of the signals vector. Note that the dimension property holds also for simple signals.

The format of the messages for parallel signals is the following:



where



- [1] defines a new signal composed of the signals given as parameters. A signal parameter is defined as:
 - [4] an identifier i.e. a signal name referring to an existing signal in the signal node.
 - [5] or as a float value. This form is equivalent to an anonymous constant signal holding the given value.
- [2] sets the values of the signals using a projection string. See section 15.1.3 p.58.
- [3] in addition to the get format defined for signals, a parallel signal supports the get dimension message, that gives the number of simple signals in parallel. The dimension of a simple signal is 1.

EXAMPLE

Putting a signal *y* and constant signals 0.01 0. 1. 1. 1. in parallel:

```
/ITL/scene/signal/mySig set y 0.01 0. 1. 1. 1. ;
```

Querying the previously defined parallel signal:

```
/ITL/scene/signal/mySig get ;
# will give the following output:
/ITL/scene/signal/mySig set y 0.01 0. 1. 1. 1.
```


NOTE

For a parallel signal:

- the get size message gives the maximum of the components size.
- the get default message gives the default value of the first signal.

15.1.3 Distributing data to signals in parallel

When signals are in parallel, a *projection string* may be used to distribute data over each signal. Individual components of a parallel signal may be addressed using a *projection string* that is defined as follows:



The projection string is made of a *index value*, followed by an optional *parallel marker* (~), followed by an optional *step value*, all enclosed in brackets.

The *index value* n is the index of a target signal. When the *parallel marker* option is not present, the values are directed to the target signal. Indexes start at 0.

EXAMPLE

Sending data to the second component of a parallel signal:

```
/ITL/scene/signal/sig '[1]' 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0. ;
```

is equivalent to the following message (assuming that the second signal name is 's2'):

```
/ITL/scene/signal/s2 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0. ;
```

Note that:

- the message is ignored when n is greater than the number of signals in parallel. Default n value is 0.
- setting directly the values of a simple signal or as the projection of a parallel signal are equivalent.

The *parallel marker* (\sim) and the *step value* w options affect the target signals. Let's consider $s[n]$ as the signal at index n . The values are distributed in sequence and in loop to the signals $s[n]$, $s[n+w] \dots s[m]$ where m is the greatest value of the index $n+(w.i)$ that is less than the signal dimension. The default *step value* is 1.

EXAMPLE

Sending data to the second and third components of a set of 3 parallel signals:

```
/ITL/scene/signal/sig [1~] 0.1 0.2 ;
```

is equivalent to the following messages (assuming that the signal dimension is 3):

```
/ITL/scene/signal/sig [1] 0.1 ;
/ITL/scene/signal/sig [2] 0.2 ;
```


or to the following (assuming that the target signal names are 's2' and 's3'):

```
/ITL/scene/signal/s2 0.1;
/ITL/scene/signal/s3 0.2;
```

15.2 Connecting signals to graphic attributes.


A signal may be connected to one or several graphic attributes of an object. Only the common attributes (see section 3 p.7) support this mechanism. When a connection between a signal and an object attribute is set, sending values to the signal is equivalent to send the values to the connected object attribute. A similar behavior could be achieved by sending the equivalent messages, however the connection mechanism is provided for efficiency reasons and in addition, it supports values scaling.

signalcnx




- the **connect** message makes a connection between a signal and one or several attributes of one or several objects.
- the **disconnect** message breaks a specific connection [1] or all the connections of a given signal [2], or all connections between a given signal and a given object [3].

connection



- `signal` is a name referring to an existing component of the `signal` node.

target



- `object` is the name of an object (must be on the same hierarchy level than the `signal` node).
- `attribute` is the name of the object target attribute (same name as the method used to set the attribute, e.g. `x`, `angle`, etc.).
- an optional scaling feature is provided with the `[low,high]` suffix: signal values are expected to be between -1 and 1, the scaling suffix re-scale the input values between `low` and `high`.

NOTE

Connections are restricted to one-dimensional signals as source and to one-dimensional attribute as target. This is not a real limitation since any component of a multi dimensional attribute (e.g. `color`) is always available as a single attribute (e.g. `red` or `blue`).

NOTE

A connection can't cross the borders of a component i.e. the target object and the signal node should have the same parent.

EXAMPLE

Connecting signals to attributes:

```
#connects the values of sig1 to the red attribute of the 'rect' object
/ITL/scene/signal connect sig1 "rect:red";
# connects the values of sig2 to several objects and attributes
/ITL/scene/signal connect sig2 "rect:blue:x:rotatey[0,360]" "cursor:date[0,15]";
```

Disconnecting some of the previous connections :

```
/ITL/scene/signal disconnect sig2 "cursor:date" "rect:rotatey:blue";
```

15.3 Graphic signals.


A graphic signal is the graphic representation of a set of parallel signals. It is created in the standard scene address space. A simple graphic signal is defined by a parallel signal controlling the `y` deviation value, the thickness and the color at each time position. The color is encoded as HSBA colors (Hue, Saturation, Brightness, Transparency). The mapping of a signal value (`[-1,1]`) to the HSBA color space is given by the table 15.1.

Table 15.1: HSBA color values.

parameter	mapping	
hue	<code>[-1,1]</code>	corresponds to <code>[-180,180]</code> angular degree where 0 is red.
saturation	<code>[-1,1]</code>	corresponds 0% to 100% saturation.
brighthness	<code>[-1,1]</code>	corresponds 0% (black) to 100% (white) brithgness.
transparency	<code>[-1,1]</code>	corresponds 0% to 100% tranparency.

A graphic signal responds to common component messages (section 3 p.7). Its specific messages are the following:

graphicSignal







Figure 15.2: The HSB color space

- the `set` message is followed by the graph type and a *signalIdentifier*, where *signalIdentifier* must correspond to an existing signal from the signal address space. In case *signalIdentifier* doesn't exist, then a new signal is created at the *signalIdentifier* address with default values.
- the `get dimension` message gives the number of graphic signals in parallel (see section 15.3.2 p.62).

graphtype



The signal representation type is among:

- `graph`: a classical signal representation as illustrated in figure 15.1, where time is mapped to the x coordinate.
- `fastgraph`: a representation similar to the `graph` type, using a more efficient drawing strategy, but at the expense of a degraded graphic rendering.
- `radialgraph`: a signal representation where time is mapped to the polar coordinates. The rendering takes place in the ellipse enclosed in the object dimensions.

EXAMPLE

Creating a signal and its graphic representation:

```
/ITL/scene/signal/y size 200 ;
# use of constant anonymous signals for thickness and color
/ITL/scene/signal/sig set y 0.1 0. 1. 1. 1. ;
/ITL/scene/siggraph set graph sig ;
```

15.3.1 Graphic signal default values.

As mentioned above, a graphic signal expects to be connected to parallel signals having at least an *y* component, a graphic thickness component and HSBA components. Thus, from graphic signal viewpoint, the expected dimension of a signal should be equal or greater than 6. In case the *signalIdentifier* dimension is less than 6, the graphic signal will use the default values defined in table 15.2.

Table 15.2: Graphic signal default values.

parameter	default value	
y	0	the center line of the graphic
thickness	0	
hue	0	meaningless due to brightness value
saturation	0	meaningless due to brightness value
brightness	-1	black
transparency	1	opaque

15.3.2 Parallel graphic signals.

When the dimension d of a signal connected to a graphic signal is greater than 6, then the input signal is interpreted like parallel graphic signals. More generally, the dimension n of a graphic signal is:

$$n \mid n \in \mathbb{N} \wedge 6.(n-1) < d \leq 6.n$$

where d is the dimension of the input signal.

When d is not a mutiple of 6, then the last graphic signal makes use of the default values mentionned above.

EXAMPLE

Creating parallel graphic signals:

```
/ITL/scene/signal/y1 size 200 ;
/ITL/scene/signal/y2 size 200 ;
# use of constant anonymous signals for thickness and color
/ITL/scene/signal/sig1 set y1 0.1 0. 1. 1. 1. ;
# use a different color for 'sig2'
/ITL/scene/signal/sig2 set y2 0.1 0.6 1. 1. 1. ;
# put 'sig1' and 'sig2' in parallel
/ITL/scene/signal/sig set sig1 sig2;      #'sig' dimension is 12
/ITL/scene/siggraph set graph sig;
```

NOTE

Using data projection may be convenient when the input signal represents interleaved data. For example, the projection string $[n \sim 6]$ distribute data over similar components of a set of graphic signals, where n represents the index of the graphic signal target component.

Chapter 16

Sensors

INScore supports various sensors, which can be viewed as objects or as signals. When created as a signal node, a sensor behaves like any signal but may provide some additional features (like calibration). When created as a score element, a sensor has no graphical appearance and provides specific sensor events and features.

Table 16 gives the list of supported sensors names.

name	values	description
accelerometer	x, y, z	acceleration on the x, y, and z axis
ambient light	light level	ambient light value
compass	azimuth,	azimuth is in degrees from magnetic north in a clockwise direction
gyroscope	x, y, z	the angular velocity around the x, y, and z axis
light	lux	the light level measured as lux
magnetometer	x, y, z	the raw magnetic flux density measured on th x, y and z axis
orientation	orientation	the device orientation
proximity	close	a boolean value
rotation	x, y, z	the rotation around the x, y and z axis
tilt	x, y	the amount of tilt on the x and y axis.

Table 16.1: Sensors names and description

NOTE

All the sensors won't likely be available on a given device. In case a sensor is not supported, an error message is generated at creation request and the creation process fails.

16.1 Sensors as signals

A sensor is viewed as a signal when created in a `signal` node using pre-defined signal names which are listed in table 16.1. Values provided on different axis (e.g. acceleration on the x, y, and z axis) are available from the sensor subnodes, also listed this table.

EXAMPLE

Creating a rotation sensor with a 200 values buffer size.

```
/ITL/scene/signal/rotation size 200;
```

Getting accelerometer values on the x axis.

```
/ITL/scene/signal/accelerometer/x get;
```

NOTE


The `rotation` sensor may or may not have a z component however, the z signal is always present but set to 0 when no z component is available. A specific message is provided to get the z component status (see section 16.6.3 p.67).

sensor	signal name	subnodes
accelerometer	accelerometer	x, y, z
ambient light	ambientlight	none
compass	compass	none
gyroscope	gyroscope	x, y, z
light	light	none
magnetometer	magnetometer	x, y, z
orientation	orientation	none
proximity	proximity	none
rotation	rotation	x, y, [z]
tilt	tilt	x, y

Table 16.2: Sensor's signal names and subnodes

16.2 Sensors as nodes

A sensor is viewed as a regular INScore node when created outside a signal node and using one of the sensors types defined below. A sensor node has no graphical appearance but has the position attributes of an INScore object (x, y, z and scale).



Values generated by a sensor are available using its x, y and z attributes. Depending on the sensor type, y and z may be useless. Note also that events generated in the context of a sensor have the variables \$x, \$y and \$z set with the current sensor values (see section 17.5.2 p.75).

EXAMPLE

Creating a proximity sensor, querying it's value and watching the value changes.

```

/ITL/scene/sensor set proximity;
/ITL/scene/sensor get x;
/ITL/scene/sensor watch newData (/ITL/scene/score show '$x');

```

16.3 Values

Values generated by the sensors depends on the sensor type and on the the sensor instance (i.e. whether created as signal or as node). Table 16.3 presents the values range for the node and the signal instances. The rationale is that nodes values are raw sensor values while signal values are mapped to the signal range i.e. [-1,1]. Actually,

sensor	node values	signal values	comment
accelerometer	[-v,v]	[-1,1]	depends on the calibration
ambient light	0,1,2,3,4,5	[-1,1]	see the note about ambient light below
compass	[-180,180]	[-1,1]	
gyroscope	[-v,v]	[-1,1]	depends on the calibration
light	[0,v]	[-1,1]	depends on the calibration
magnetometer	[-v,v]	[-1,1]	
orientation	0,1,2,3,4,5,6	[-1,1]	see the note about orientation below
proximity	0,1	[-1,1]	a boolean value mapped to -1, 1
rotation	x [-90, 90]	[-1,1]	
	y [-180, 180]	[-1,1]	
	z [-180, 180]	[-1,1]	
tilt	[-90,90]	[-1,1]	

Table 16.3: Sensor's values as node and as signal

the mapping of the raw values depends on the sensor calibration that can be automatically or manually adjusted. See the section about calibration below.

NOTE ABOUT AMBIENT LIGHT

Ambient light is measured using discrete values ranging from 0 to 5, where 0 means undefined and 1 to 5 goes from dark to very bright.

A value v is mapped to $(v * 0.4 - 1)$

NOTE ABOUT ORIENTATION

Orientation is measured using discrete values ranging from 0 to 6, where 0 means undefined and 1 to 6 represents the following orientations:

- 1: the Top edge of the device is pointing up.
- 2: the Face of the device is pointing up.
- 3: the Left edge of the device is pointing up.
- 4: the Face of the device is pointing down.
- 5: the Right edge of the device is pointing up.
- 6: the Top edge of the device is pointing down.

A value v is mapped to $(v/3 - 1)$

In a given way and from values 2 to 5, the device may be viewed as rotating clockwise. A counter-clockwise option is also supported, see section 16.6.4 p.67.

16.4 Calibration

Calibration of sensor values may be viewed as scaling and makes use of the common object's `scale` attribute. By default, the scale value is 1.0 when the sensor is a regular node. For signal nodes, the default scale value is given by the table 16.4. These values have been chosen to map the raw values to the signal range but of course this mapping depends on the device and may greatly vary. In order to accommodate these variations but also to cope with different requirements, scaling can be manually adjusted to any arbitrary value using the `scale` message, or automatically adjusted to measured peak values using the `autoscale` message.

NOTE ABOUT AUTO-SCALING

Auto-scaling consists in measuring the peak of the absolute values of a sensor during a period. The sensor scale value is next adjusted to $1/peak$ (see also the sensor common messages in section 16.5). Auto-scaling is supported by all the sensors, although


16.5 Sensor common messages

All sensors support a common set of message.

sensor	signal scale	comment
accelerometer	1/g	where g is the gravity on earth i.e. 9.81
ambient light	0.4	see the note about ambient light above
compass	1 / 180	
gyroscope	1 / 90	
light	1 / 200	an arbitrary lux value (considered as
magnetometer	10000	
orientation	1/3	see the note about orientation above
proximity	1.0	the false value is shifted to -1
rotation	1 / 180	for the x value, the scale is multiplied by 2
tilt	1 / 90	

Table 16.4: Sensor as signal default scaling

sensorCommon




- **run:** takes a boolean value as parameter. When true, the sensor starts to generate values. Default value is false.
- **smooth:** applies exponential smoothing to the sensor values. At a time t , the sensor value is computed as: $s_t = \alpha \cdot v_t + (1 - \alpha) \cdot s_{t-1}$ where v_t is the current sensor value and $0 \leq \alpha \leq 1$. The parameter is the smoothing factor α . Default value is 1.
- **scale:** sensor values are multiplied by the scale. Default scale is dependent on the sensor type. See table 16.4 for the default scale values.
- **autoscale:** start or stop the auto-scaling process. Default value is false. See the note about auto scaling above. Note that a sensor must be running for the auto-scaling process to take effect.
- **reset:** reset the smoothing factor and the scale to their default values.

16.6 Sensor specific messages

16.6.1 Accelerometer sensor

accelerometerMsg



- **mode:** the acceleration mode controls how acceleration values are reported.
 - **gravity:** only the acceleration caused by gravity is reported. Movements of the device caused by the user have no effect other than changing the direction when the device is rotated.
 - **user:** only the acceleration caused by the user moving the device is reported, the effect of gravity is canceled out. A device at rest therefore should report values of, or close to, zero.
 - **combined:** both the acceleration caused by gravity and the acceleration caused by the user moving the device is reported combined.


Default value is `combined`.

NOTE ABOUT MODES

Acceleration caused by gravity and acceleration caused by the user moving the device are physically impossible to distinguish because of general relativity. Most devices use sensor fusion to figure out which parts of the acceleration is caused by gravity, for example by using a rotation sensor to calculate the gravity direction and assuming a fixed magnitude for gravity. Therefore the result is only an approximation and may be inaccurate. The `combined` mode is the most accurate one, as it does not involve approximating the gravity.

16.6.2 Magnetometer sensor

magnetometerMsg



The magnetometer can report on either raw magnetic flux values or geomagnetic flux values. The primary difference between raw and geomagnetic values is that extra processing is done to eliminate local magnetic interference from the geomagnetic values so they represent only the effect of the Earth's magnetic field. This process is not perfect and the accuracy of each reading may change. Default value is `raw`.

16.6.3 Rotation sensor


rotationMsg



z angle availability of the rotation sensor can be queried using `hasZ`. The returned value is a boolean value.

16.6.4 Orientation sensor

orientationMsg




- `mode`: selects how the device position is mapped to successive values. Default value is `clockwise`. See table 16.6.4 for the detail of the positions and values.

value	clockwise	counter clockwise
1	Top edge up	Top edge up
2	Face up	Face up
3	Left edge up	Right edge up
4	Face down	Face down
5	Right edge up	Left edge up
6	Top edge down	Top edge down

Table 16.5: Device positions and values in different modes.

16.6.5 Tilt sensor

tiltMsg



- `calibrate`: calibrates the tilt sensor: uses the current tilt angles as 0.

Chapter 17


Events and Interaction

Interaction messages are user defined messages associated to *events* and triggered when these events occur. These messages accept variables as message arguments.

Events are typical user interface events (mouse or touch events), extended in the time domain and to specific objects or engine properties. Starting from INScore version 1.20, the modification of any object attribute may be viewed as an event and user defined events have also been introduced (see section 17.2 p.72 for more details).

The general form of the message to *watch* an event is the following:

interactMsg



what represents the event to watch and *message* is a list of associated messages, separated by a comma. A colon (':') is also supported as separator (to avoid issues with comma in Max).

- 1 : clear all the messages for all the events.
- 2 : clear the messages associated to the *what* event.
- 3 : associate a list of messages to the *what* event. With *watch*, the messages replace previously associated messages. Using *watch+*, the messages are appended to the messages currently associated to the event.
- 4 : associate or add a single message to the *what* event. This form is provided for compatibility with previous versions.


NOTE

The [1] and [2] form has no effect with the *watch+* message.

In some environments, the comma has a special meaning, making tricky to use it as a message separator. This is why ':' is also accepted as separator in OSC messages lists.


The *get watch* message gives all the watch messages of a node, but doesn't take any argument.

message



The associated messages are any valid OSC message (not restricted to the INScore message set), with an extended address scheme, supporting IP addresses or host names and udp port number to be specified as OSC addresses prefix. The message parameters are any valid OSC type or variable (see section 17.5).

addressPrefix



EXAMPLE

An extended address to send messages to localhost on port 12000:

```
localhost:12000/your/osc/address;
```


17.1 Internal events

Internal events are triggered by the user interaction (mouse or touch events) or by the engine internal functioning.

17.1.1 Mouse events

User interface events are typical mouse events:

mouseEvent



EXAMPLE

Triggering a message on mouse down:

```
/ITL/scene/myObject watch mouseDown (/ITL/scene/myObject show 0);
```

the object hides itself on mouse click.

Triggering a message on mouse down but addressed to another host on udp port 12100:


```
/ITL/scene/myObject watch mouseDown (host.domain.org:12100/an/address start);
```

NOTE

UI events are not supported by objects that are synchronized as slave.

Mouse events can be simulated using a `event` message:

uievt



where `mouseEvent` is one of the events described above, `x` and `y` are integer values giving the click position, expressed in pixels and relative to the target object.

EXAMPLE


Simulating a mouse down at position 10, 10 :

```
/ITL/scene/myObject event mouseDown 10 10;
```

17.1.2 Touch events

Depending on the display device, multi-touch events are supported by INScore :

touchEvent




A typical sequence of generated events consists in a *touchBegin* event, followed by *touchUpdate* events and closed by a *touchEnd*.

17.1.3 Time events

Events are also defined on the time domain:

timeEvent



Each event takes a time interval as parameter, defined by two *time* specifications (see section 4 p.17 for the time format)

- *timeEnter*, *timeLeave* are triggered when an object date is moved to or out of a watched time interval,
- *durEnter*, *durLeave* are triggered when an object duration is moved to or out of a watched time interval.

EXAMPLE


An object that moves a score to a given page number when it enters its time zone.

```
/ITL/scene/myObject watch timeEnter 10/1 18/1 (/ITL/scene/score page 2);
```


17.1.4 Keyboard events

Keyboard events are triggered by pressing or releasing a key on the keyboard.

keyEvent



controlKey



- 1) only the specified `char` will trigger the event,
- 2) `charlist` is a string interpreted like the bracket expression of regular expressions. For example, using `[abc]`, 'a' or 'b' or 'c' will trigger a key event, using `[1-9]`, any numeric from 1 to 9 will trigger a key event.
- 3) any key triggers a key event.
- 4) handles special keys to trigger the key event. A literal description of the key must be provided (e.g. `ArrowLeft`).

NOTE

Unlike standard applications, there is no notion of focus regarding key events: when several objects request keyboard input, all of them will receive `key` events, provided they are watching the same input.


17.1.5 MIDI events

MIDI events are supported, but only by the Web version. MIDI events are supported by the native version for compatibility reasons but they are inactive (no MIDI input).

See INScore Web documentation for more details.

17.1.6 URL events

`url` objects (i.e. intermediate objects for URL based objects (see section 6.8 p.24) support specific events, intended to reflect the transaction state:

urlEvent

- `success` is triggered when the data have been downloaded,
- `error` is triggered when an error has occurred during the download,
- `cancel` is triggered when the target url or the object type is changed while downloading.

EXAMPLE

Triggering an error message in case of failure :

```

/ITL/scene/score set gmnf "http://ahost.adomain.org/score.gmn";
/ITL/scene/score watch error(
  /ITL/scene/status set txt "Failed to download file"
);


```

17.1.7 Miscellaneous events*miscEvent*

- the `export` event is supported by all the components. It is triggered after an export message has been handled and could be used to simulate synchronous exports.
- the `newData` event is supported by all the components. It is triggered when the object specific data are modified (typically using the `set` message).

17.1.8 Type specific events

specificEvent



- the `pageCount` event is supported by all the symbolic score components (`gmn(f)`, `gmnstream`, `musicxml(f)`). It is triggered when the page count of the score changes. It is mainly intended to manage variable scores like `gmnstream`.
- the `newElement` event is supported at scene level only and triggered when a new element is added to the scene.
- the `endPaint` event is supported at scene level only and triggered after a scene has been painted.
- the `error` event is supported at application level and triggered when an error occurs while receiving messages. Typically you can use of this event to open the log window (`/ITL/log show 1`)
- the `ready` event is supported by media objects (audio and video). It is triggered when media data (duration, graphic dimensions) are available.
- the `end` event is supported by media objects (audio and video). It is triggered when a media is playing and reaches the end of the media. In this case, the object play status is automatically switched to 0 to reflect the actual player state.

EXAMPLE

Displaying a welcome message to new elements:

```
/ITL/scene watch newElement (/ITL/scene/msg set txt "Welcome");
```

17.2 Attribute based events

Attribute based events includes the whole set of messages that are supported by an object: `x`, `y`, `color`, etc. but also type specific messages. These events are triggered when a message has been successfully processed. However, you shouldn't assume that the attribute value has been changed: when a message sets an attribute to its current value, it is successfully processed and the corresponding event - if any - is triggered.

EXAMPLE

Watching an object `x` coordinate change:

```
/ITL/scene/myObject watch x (/ITL/scene/msg set txt "myObject moved");
```

NOTE

Watching the `newData` event is equivalent to watch the `set` attribute. However, the `newData` event is triggered only when the object state is changed.

WARNING

With the event's generalization to any object attribute, a one tick delay has been introduced to all events. Thus the associated messages are not processed synchronously to the event but posted to be processed by the next time task. This delay has been introduced to avoid freezing the system in case of loops. However, it introduces also a pitfall in interaction design, when message based variables are used (see section 17.5.5 p.76): message based variables are evaluated at the event time while messages are processed by the next time task, thus the following messages won't produce the expected result:

```

/ITL/scene/myObject watch x (
  /ITL/scene/A x '$(/ITL/scene/myObject get x)',
  /ITL/scene/B x '$(/ITL/scene/A get x)'
);

```

actually, when the `$(/ITL/scene/A get x)` variable is evaluated, the preceding message that sets the `x` attribute of `A` has not been already processed. One workaround consists in splitting the interaction in several parts, making sure that the messages are processed e.g.

```

/ITL/scene/myObject watch x ( /ITL/scene/A x '$(/ITL/scene/myObject get x)');
/ITL/scene/A watch x ( /ITL/scene/B x '$(/ITL/scene/A get x)' );

```

17.3 User defined events

INScore events supports user defined events. The name of user defined events must start with a capital letter and be composed of capital letters and/or numbers. Other characters are reserved for INScore use.

Messages attached to user defined events accept regular variables (although the position variables are useless), but they accept also any number of a variables which names are `$1`, ... `$i` and which values are taken from the event call arguments (see section 17.5.6 p.76).

User defined events can only be triggered using the `event` message (see section 17.4 p.73).

EXAMPLE

Watching and triggering a user defined event:

```

/ITL/scene/myObject watch MYEVENT (/ITL/scene/msg set txt "MYEVENT occurred!");
/ITL/scene/myObject event MYEVENT;

```

Defining high level abstractions:

```


/ITL/scene/myObject watch MOVEABC (
  /ITL/scene/a x $1,
  /ITL/scene/b x $2,
  /ITL/scene/C x $3
);
/ITL/scene/myObject event MOVEABC -0.4 0.1 0.6;

```

17.4 The 'event' message

The `event` message may be used to triggered events. It's the only way to trigger user defined events. It may be used also to simulate user interface events (like mouse events).

eventMsg



- **1:** this form is intended to simulate mouse or touch event. It must be followed by the `x` and `y` coordinates of the interaction point. Coordinates express a position in pixels (the top left corner of the object is in `[0,0]`).
- **2:** triggers a user defined event. It accepts any number of arguments, that are then expanded in place of the variables `$1` ... `$i`. User defined events may be viewed as functions with arbitrary parameters; however parameters count and type is not checked.

- **3**: triggers any other event.

NOTE

Time events are excluded from the `event` message supported events: to trigger a time event, you can use a `date` message.


17.5 Variables

Variables are values computed when an event is triggered. These values are send in place of the variable. A variable name starts with a '\$' sign.

17.5.1 Position variables


Position variables reflects the current mouse position for mouse events or the current touch position for touch events. For attribute based events, the `x` and `y` variables are set to the target object current position and the other variables are undefined. For other events, the position variables are set to 0.

posVar



where

xy



- `$x $y`: denotes the mouse pointer position at the time of the event. The values are in the range `[0,1]` where 1 is the object size in the `x` or `y` dimension. The value is computed according to the object origin: it represents the mouse pointer distance from the object `x` or `y` origin (see 3.1.3 p.10). `$x` and `$y` variables support an optional range in the form `[low, high]` that transforms the `[0,1]` values range into the `[low, high]` range.
- `$absx $absy`: denotes the mouse pointer absolute position at the time of the event. The values represent a pixel position relative to the top-left point of the target object. Note that this position is unaffected by scale. Note also that the values are not clipped to the object dimensions and could exceed its width or height or become negative in case of mouse move events.
- `$sx $sy`: denotes the mouse pointer position in the scene coordinates space.

EXAMPLE


An object that follows mouse move.

```
/ITL/scene/myObject watch mouseDown (
    /ITL/scene/myObject x '$sx',
    /ITL/scene/myObject y '$sy' );
```


17.5.2 Sensor variables

Sensors values are available using the `$x`, `$y` and `$z` variables, for events generated in the context of a sensor.

xyz




Note that depending on the sensor type, the `$y` and `$z` variables may be useless.

17.5.3 Time variables

Time variables reflects the date corresponding to the current mouse position for mouse events. For attribute based events, the time variables are set to the target object current time position. They are set to 0 for the other events.

timeVar



- `$date`: denotes the object date corresponding to the mouse pointer position at the time of the event. It is optionnally followed by a colon and the name of the mapping to be used to compute the date. The `$date` variable is replaced by its rational value (i.e. two integers values). The optional rational enclosed in brackets may be used to indicate a quantification: the date value is rounded to an integer count of the specified rational value. The optional `%f` may be used to get the date delivered as a float value.
- `$rdate`: is similar to `$date` but ignores the target current date: the date is relative to the object mapping only.

NOTE

A variable can be used several times in a message, but several `$date` variables must always refer to the same mapping.


EXAMPLE

Sending the current date as a float value to an external application:

```
/ITL/scene/myObject watch mouseDown ( targetHost:12000/date '$date%f' );
```

17.5.4 Miscellaneous variables

variable



- `$name` is replaced by the target object name.
- `$scene` is replaced by the target object scene name.
- `$address` is replaced by the target object OSC address.

NOTE

For the `newElement` event, the target object is the new element.

EXAMPLE


Using an object name:

```
/ITL/scene watch newElement (/ITL/scene/welcome set txt "Welcome" '$name');
```

17.5.5 Message based variables

A message based variable is a variable containing an OSC message which will be evaluated at the time of the event. They are supported by all kind of events. Like the variables above, a message based variable starts with a '\$' sign followed by a valid 'get' message enclosed in parenthesis:

msgVar



The evaluation of a 'get' message produces a message or a list of messages. The message based variable will be replaced by the parameters of the messages resulting from the evaluation of the 'get' message. Note that all the 'get' messages attached to an event are evaluated at the same time.

EXAMPLE

An object that takes the x position of another object on mouse down:

```
/ITL/scene/myObject watch mouseDown
(/ITL/scene/myObject x '$(/ITL/scene/obj get x)');
```

17.5.6 Variables for user defined events

Messages associated to user defined events accept any number of a variables which names are \$1, ... \$i and which values are taken from the event call arguments. These events may be viewed as functions with arbitrary parameters; however parameters count and type is not checked: arguments in excess are ignored and variables without corresponding argument (e.g. \$3 when only 2 arguments are available) are left unexpanded.

17.5.7 OSC address variables

The OSC address of a message associated to an event supports the following variables:

- \$self: replaced by the object name.
- \$scene: replaced by the scene name.

EXAMPLE


Requesting a set of objects to send a message to themselves on a mouse event:

```
/ITL/scene/* watch mouseDown #request all the objects of the scene
(/ITL/scene/$self x '$sx'); #to send a message to themselves
```

17.6 Interaction state management

For a given object, its *interaction state* (i.e. the watched events and the associated messages) can be saved and restored.

stateMsg




Interaction states are managed using a stack where the states are pushed to or popped from.

- push: push the current interaction state on top of the stack.
- pop: replace the current interaction state with the one popped from the top of the stack.

The different states stored in this stack can be obtain with the message :

stackMsg



NOTE

The effect of a pop message addressed to an object with an empty stack is to clear the object current interaction state.


17.7 File watcher

The *fileWatcher* is a static node of a scene that is intended to watch file modifications.

It receives messages at the address `/ITL/scene/fileWatcher`.

The *fileWatcher* support the `watch` and `watch+` messages as described in section 17 p.68 with a file name used in place of the `what` parameter.

fileWatcher



EXAMPLE

Reload an INScore script on file modification:

```
/ITL/scene/fileWatcher watch 'myScript.inscore'
( /ITL/scene load 'myScript.inscore' );
```

NOTE

Some text editors delete the target file before saving. In this case, it breaks the file watching system and thus, it doesn't work as expected.

Chapter 18

Score expressions

Score expressions allows to defines score objects (`gmn` or `pianoroll`) by dynamically combine various resources using a formal expression. To define such object one should use the basic `set` messages using a score expressions as arguments:

EXAMPLE


The following example defines a `gmn` and a `pianoroll` object using score expressions, the meaning of the expression is explained further.

```
/ITL/scene/score set gmn expr(seq [a] [b]);  
/ITL/scene/pianoroll set pianoroll expr(score);
```

18.1 General Syntax

A score expression always starts with `expr (` and ends with `)`, then 2 syntaxes are handled:

EvaluableExpression



- **1:** Define an expression as an operation combining two scores. `operator` is the name of the operation used to combine them (see Section 18.2 for operators list), and `score` are the arguments passed to the operator (see Section 18.3 for arguments specification).
- **2:** Define on expression using a single score. This syntax is useful when defining an object as a dynamic copy of an other existing object or file.

Each of these tokens can, of course, be separated by spaces, tabulations or carriage returns (allowing multiline expression definition).

When defining an object using a score expressions, `INScore` will parse it, construct an internal representation and finally evaluate it, reducing the formal expressions to a valid GMN string.

EXAMPLE

Creating a guido object by sequencing two guido string

```
/ITL/scene/score set gmn expr( seq "[c d e]" "[f g h]");
```

is equivalent to

```
/ITL/scene/score set gmn "[c d e f g h]";
```

18.2 Score Operators


All the score operators of `INScore` make use of guido operators implemented in the GuidoAR library.

operation	arguments	description
seq	<i>s1 s2</i>	puts the scores <i>s1</i> and <i>s2</i> in sequence
par	<i>s1 s2</i>	puts the scores <i>s1</i> and <i>s2</i> in parallel
rpar	<i>s1 s2</i>	puts the scores <i>s1</i> and <i>s2</i> in parallel, right aligned
top	<i>s1 s2</i>	takes the <i>n</i> first voices of <i>s1</i> where <i>n</i> is <i>s2</i> voices count
bottom	<i>s1 s2</i>	cut the <i>n</i> first voices of <i>s1</i> where <i>n</i> is <i>s2</i> voices count
head	<i>s1 s2</i>	takes the head of <i>s1</i> up to <i>s2</i> duration
evhead	<i>s1 s2</i>	takes the <i>n</i> first events of <i>s1</i> where <i>n</i> is the event's count of <i>s2</i>
tail	<i>s1 s2</i>	cut the beginning of <i>s1</i> up to the duration of <i>s2</i>
evtail	<i>s1 s2</i>	cut the <i>n</i> first events of <i>s1</i> where <i>n</i> is the event's count of <i>s2</i>
transpose	<i>s1 s2</i>	transposes <i>s1</i> so its first note of its first voice match <i>s2</i> one
duration	<i>s1 s2</i>	stretches <i>s1</i> to the duration of <i>s2</i>
		if not used carefully, this operator can output impossible to display rhythm
pitch	<i>s1 s2</i>	applies the pitches of <i>s1</i> to <i>s2</i> in a loop
rhythm	<i>s1 s2</i>	applies the rhythm of <i>s1</i> to <i>s2</i> in a loop

18.3 Score Arguments

The syntax for arguments is quite permissive and various resources can be used as arguments for score expressions. In any case, when evaluating the expression, all the arguments will be reduce to GMN string so they can then be processed by the operators.

Argument



Arguments specification

- `GmnCode` are not evaluated, passed as they are to operators. Both GMN and MusicXML string are supported.
- `filepath`: on evaluation INScore read all the content of the file. Again, both GMN and MusicXML are supported. `filepath` handle absolute or relative path (from the scene `rootPath`) as well as url.
- `ScoreObject`: Gmn code can be retrieve from existing score objects (`gmn` or `pianoroll`) simply refering to them using their identifier (using absolute or relative path).
- `EvaluableExpression`: an expression can also be used as an argument, thus simple operator can be combined together to create more complex ones. In that case the `expr` token can be omitted: parenthesis are sufficient.

Arguments prefix

- `&`: When triggering the reevaluation of an expression (see Section 18.4) only the arguments prefixed with `&` are updated.
- `~`: before the first evaluation of a score expression, any `ScoreObjects` prefixed with a `~` shall be replaced by their own expression. In other words, score expressions containing `~` arguments will be expended with existing score expressions. This mechanism allows to compose not only scores and score expressions together.

EXAMPLE

Defining `/ITL/scene/score` as a copy of `/ITL/scene/simpleScore` duplicated 4 times.

```
/ITL/scene/simpleScore set gmn "[e {c,g} |]";  
  
/ITL/scene/score set gmn expr( &simpleScore );  
/ITL/scene/score set gmn expr( seq ~score ~score);  
/ITL/scene/score set gmn expr( par ~score ~score);
```

/ITL/scene/score should look like:



Querying for the expanded expression of /ITL/scene/score (see Section 18.4) should return:

```
/ITL/scene/score expr  
  expr( par  
    ( seq  
      &simpleScore  
      &simpleScore  
    )  
    ( seq  
      &simpleScore  
      &simpleScore  
    )  
  )
```

NOTE ON ARGUMENTS QUOTING

Arguments using special characters (space, tabulation, parenthesis, braces...), should be simple or double quoted, otherwise quotes can be omitted.

18.4 'expr' commands

ITLObject defined using an evaluable expression gain access to these specific commands:

- `get expr`: return the expression used to define the object (before the expansion of ~ arguments).
- `get exprTree`: return the expanded expression
- `expr reeval`: re-evaluate the expression, updating only the value of arguments prefixed with &.
- `expr reset`: re-evaluate the expression, updating the value of all arguments.
- `expr renew`: reapply the definition of the object (similar to send its `set` message again)

Applied to an object which wasn't defined by an evaluable expression, all this commands will cause a bad argument error.

The `renew` command reset the internal state of the evaluated variable, forcing the re-evaluation and update of every arguments in the expression. Be aware that the track of copy evaluated arguments is lost after the first evaluation, thus renewing an expression defined using copy evaluated arguments won't update these arguments to their targeted ITLObject expression. Though, static arguments added by the copy shall be renewed.

18.5 newData event

`newData` is triggered by any object when its value change (generally because of a `set` message). Neither trying to set an object to its actual value without changing its type, nor re-evaluating an object to its actual value will

trigger `newData`.

Of course, the `newData` event can be used together with `reeval` to automatically update an object when the value of an other changes.

EXAMPLE

Creating a copy of `score`, and automatise its update when `score` is changed

```
/ITL/scene/score set gmn "[c e]";
/ITL/scene/copy set gmn expr(&score);
/ITL/scene/score watch newData (/ITL/scene/copy expr reeval);
```

To avoid infinite loop when using recursion, `newData` event is delayed of one event loop, meaning that, in the previous example, during the event loop that follow `score`'s modification, `score` and `copy` are different (`copy` has not been updated yet...).

NOTE

Because `newData` event is delayed, if `score` experiences multiple modifications during the same event loop (because multiple `set` messages have been sent together), only his final value will be accessible when `newData` will be actually triggered, however the event will be sent as many times as `score` have been modified.

NOTE WHEN AUTOMATIZING UPDATE

For the reasons raised in the previous note, one should be very careful to delayed update when automatise `reeval` with `newData`. Indeed, in some extreme case, executing a script one line after an other won't have the same result as executing the all script at once!!

EXAMPLE

Creating a "score buffer", storing every state adopted by `score`

```
/ITL/scene/score set gmn "[c]";

/ITL/scene/buffer set gmn "[]";
/ITL/scene/buffer set gmn expr(seq &buffer (seq "[]" &score));
/ITL/scene/score watch newData (/ITL/scene/buffer expr reeval);

/ITL/scene/score set gmn "[e]";
/ITL/scene/score set gmn "[g]";
/ITL/scene/score set gmn "[{c,e,g}]";
```

Won't have the same result if run line by line, or the all script as once:

Line by line:



All script lines at once:



To avoid such undeterministic behaviour, one should, in this case, manually trigger `reeval` after each modification of `score`.

Chapter 19

Plugins

A plugin is an external library that is dynamically loaded when an object that need it is created. The system looks for plugins in the following locations:

- in the current folder first
- in the PlugIns folder, located in the application bundle on macos, in the application folder on other systems
- in the system default locations for shared libraries

Additionally, a user path can be set, where the system will look for plugins in first position. See section 9.5.4 p.41. The plugins are shared libraries which extension is platform dependent. The plugin name should not include the extension. The expected extensions are the following: .dylib on MacOS and Linux, .dll on Windows.

19.1 FAUST plugins


FAUST [Functional Audio Stream] is a functional programming language specifically designed for real-time signal processing and synthesis. A FAUST/INScore architecture allows to embed FAUST processors in INScore, for the purpose of signals computation. A FAUST plugin is viewed as a parallel signal and thus it is created in the signal address space. Similarly to signals, it is associated to an OSC address in the form `/ITL/scene/signal/name` where *name* is a user defined name.

19.1.1 Set Message

There are two ways to create a FAUST Processor :

- 1 - By charging a DSP as a plugin already compiled

faustprocessor



EXAMPLE


```
/ITL/scene/signal/myFaust set faust aFaustPlugin;
```

NOTE


The plugin name should not include the extension. The expected extensions are the following: .dylib on MacOS and Linux, .dll on Windows.

- 2 - By charging libfaust as a plugin to compile a DSP on-the-fly (as a string or a file).

faustdsp



faustdspfile




```
/ITL/scene/signal/plus set faustdsp "process+=;";
/ITL/scene/signal/mydsp set faustdspf "mydsp.dsp";
```

19.1.2 Specific messages

A FAUST processor is characterized by the numbers of input and output channels and by a set of parameters. Each parameter carries a name defined by the FAUST processor. The set of messages supported by a FAUST processor is the set of signals messages extended with the parameters names and with specific query messages.

faustmessage



- 1 *msg* is any of the FAUST processor parameters, which are defined by the FAUST processor.
- 2 the *get* message is extended to query the FAUST processor: *in* and *out* give the number of input and output channels.

EXAMPLE

Querying a FAUST processor input and output count:

```
/ITL/scene/signal/myFaust get in out;
```

gives as output:

```
/ITL/scene/signal/myFaust in 2;
/ITL/scene/signal/myFaust out 4;
```

Modifying the value of a FAUST processor parameter named *volume*:


```
/ITL/scene/signal/myFaust volume 0.8
```

19.1.3 Feeding and composing FAUST processors

A FAUST processor accepts float values as input, which are taken as interleaved data and distributed to the input channels.

From composition viewpoint, a FAUST processor is a parallel signal which dimension is the number of output channels. Thus, a FAUST processor can be used like any parallel signal. However, the signal identifier defined in 15.1.2 is extended to support addressing single components of parallel signal as follows:

signal



where *n* selects the signal #*n* of a parallel signal. Note that indexes start at 0.

EXAMPLE

Creating 3 parallel signals using the 3 output channels of a FAUST processor named *myFaust*:

```
/ITL/scene/signal/y1 set 'myFaust/0' 0.01 0. 1. 1. 1. ;  
/ITL/scene/signal/y2 set 'myFaust/1' 0.01 0.5 1. 1. 1. ;  
/ITL/scene/signal/y3 set 'myFaust/2' 0.01 -0.5 1. 1. 1. ;
```

19.2 Gesture Follower

INScore supports gesture following using the technology developed by the IRCAM IMTR team. These features are available as a plugin that is included in the INScore distribution (version 1.03 or greater) or available from the IRCAM.

19.2.1 Basic principle

Gesture following is provided as a mean to interact with a score. From input viewpoint, the gesture follower is similar to signals (see section 15.1.1 p.57): it accepts data stream as input both in learning and following modes. It implements a specific set of events related to gesture following and can generate message streams parametrized with the gesture follower current state.

A gesture follower is setup to handle a given count of gestures, which are actually denoted by streams of float vectors. We'll refer to the size of the float vector as the *gesture dimension*. For example, the dimension of a gesture captured from x, y and z accelerometers is 3.


A gesture follower operates in two distinct phases: a *learning phase* where it actually stores the gestures data, and a *following phase* where it tries to match incoming data to the stored gestures data. When not learning nor following, we'll talk of an idle phase.

In the *following phase*, the system maintains a list of likelihood for the learned gestures, a list of positions in the gestures and a list of speeds representing how fast the gestures are made. Of course, the higher the likelihood, the more these data are meaningful. It's the user responsibility to decide on the meaningful likelihood threshold value. Interaction events are triggered only in the *following phase* and for meaningful likelihoods.

19.2.2 Messages

A gesture follower is created in a scene using the `imtrgf` type. It has a graphic appearance that may be used for debug purpose but it is hidden by default.

gesturefollower




The parameters are:

- `gesturedimension`: the size of the gestures data vector.
- `bufsize`: the size of the gesture data storage.
- `name`: a list of names to be used to refer to the learned gestures.

NOTE

A gesture follower is created with a fixed count of gestures that can be learned and decoded. These gestures are named gestures and can be addressed at `/ITL/scene/myfollower/gesturename` where the part in italic are user defined names and where *myfollower* is a gesture follower.

gesturefollowerMsgs

- [1] input data into the gesture follower. The data are interpreted according to the current operating mode i.e. learning, following or idle.
- [2] starts to learn the gesture designated by *name*. Actually records the next input data to the gesture.
- [3] starts following i.e. trying to match the next input data to the recorded gestures.
- [4] stops learning or following. Actually puts the system in idle phase.
- [5] clear all the gestures data. This is equivalent to send the `clear` message to all the gestures.
- [6] sets the size of the window that contains the history of the likelihoods. May be viewed as how fast the likelihoods will change.
- [7] sets the follower tolerance.

EXAMPLE

Creating a gesture follower for 3 dimensional data and a typical learning sequence:

```

/ITL/scene/gf set imtrgf 3 1000 gestureA gestureB gestureC gestured ;
/ITL/scene/gf learn gestureA ;
/ITL/scene/gf 0.1 0.5 -0.2 ... 0.7; #the data size must be a multiple of 3
/ITL/scene/gf stop;


```

19.2.3 Gestures management

Messages can also be sent to gestures i.e. to addresses in the form `/ITL/scene/myfollower/gesturename` where *myfollower* is a gesture follower.

A gesture could be in two states:

- an active state: when its likelihood is greater or equal to the likelihood threshold.
- an idle state: when its likelihood is lower than the likelihood threshold.

gesture

- `set`: sets the gesture data. This is equivalent to learn the corresponding data. The `set` message could be used to restored previously saved gesture data.

- `clear`: clears the gesture data.
- `learn`: puts the gestures follower in learning mode and starts learning the corresponding gesture. This is equivalent to send OSClear *gesturename* to the parent gesture follower.
- `likelihoodThreshold`: sets the gesture likelihood threshold. The parameter is a float value in the range $[0, 1]$. Default value is 0.5.

Gestures supports also specific queries :

gestureget




- `get`: without parameter, returns a set message when the gesture is not empty.
- `size`: gives the current size of the gesture, actually the number of recorded frames.

19.2.4 Events and interaction

Events are defined at gesture level and events management messages should be addressed to gestures.


gestureevents



- `gfEnter` triggered when the gesture state changes from idle to active.
- `gfLeave` triggered when the gesture state changes from active to idle.
- `gfActive` triggered in active state each time the gesture likelihood is refreshed.
- `gfIdle` triggered in idle state each time the gesture likelihood is refreshed.

A message associated to a gesture supports the following specific variables:

gesturevariable



These variables support the scaling feature associated to position variables and described in section 17.5.1 p.74.

- `gflikelihood` indicates the current likelihood
- `gfpos` indicates the current position in the gesture
- `gfspeed` indicates the current gesture execution speed

NOTE

Variables described in section 17.5 p.74 may also be used but they are meaningless and contains default values.

19.2.5 Gesture Follower Appearance

A gesture follower object has a graphic appearance and supports all the standard objects properties, including mapping and synchronization. This graphic appearance is provided mainly for debug purpose and by default, the object is hidden. Figure 19.1 shows the gesture follower appearance in its different phases:

- when idle, the upper part of the graphic indicates the buffer state of the different gestures. It also includes the gestures likelihood threshold.
- when learning, a red frame and a grey background indicates that a learning a gesture is currently in progress. The gesture buffer state is refreshed while learning.
- when following, the upper part indicates each gesture current likelihood and the lower part indicates the current estimated positions.




Figure 19.1: The gesture follower appearance in its different phases.


19.3 Httpd server plugin

INScore can embed Http server to expose real time screenshot image of a scene to the web. This feature is based on [libmicrohttpd](#) and is available as a plugin that is included in the INScore distribution (version 1.11 or greater). The Url to get the image is the base url of the server.

19.3.1 Set Message

The http server object is created in a scene like other objects and served image of his scene.

httpdserver



- port http port used by the server.

EXAMPLE

```
/ITL/scene/server set httpd 8000;
```


NOTE

If the http port is already used, the server cannot start.

19.3.2 Specific messages

The http server status can be delivered with a specific message.

httpdmessage



A string corresponding to the server status ("started" or "stopped") is return.

EXAMPLE

```
/ITL/scene/server get status;
```

Chapter 20

Changes list

20.1 Version 1.31 vs version 1.28

- add support for get 'date%f' query
- add midi node at application level, supported by the native app for compatibility reasons (works only with the web version)
- new keyDown and keyUp events
- fix \$date quantification
- fix 'event' messages forwarding
- fix \$date%f detection in javascript run method
- fix non visible mapping for images
- fix incorrect \$x et \$y variables value for proportional dimension objects
- fix missing curve rendering
- fix guido score scaling issue

INSCORE WEB SPECIFIC CHANGES

- new 'compute' message supported by faust objects
- new form of the 'connect' message (to address individual channels)
- font size unit changed to 'vw' (relative to viewport width)
- load message implemented
- new faustw object (precompiled faust dsp)
- new midi events

20.2 Version 1.28 vs version 1.27

- new dvolume method for media objects
- new ssl static application node for ssl certificates management
- new cert key cacert messages to manage ssl certificates and keys. See section 11.2 p.46
- new get clients messages at application level
- add https support to forwarding mechanism. See section 11 p.45

INSCORE WEB SPECIFIC CHANGES

- fix ready event for audio objects

20.3 Version 1.27 vs version 1.24

INSCORE WEB SPECIFIC CHANGES

- new `faust` object (web version)
- new `connect` method (web version)
- forwarding mechanism extended with http and ws support. See section 11 p.45

20.4 Version 1.24 vs version 1.22

- new `inscore2` scripting language
- log window supports the `scale` message. See section 9.5.3 p.40
- colors: supports html color names and hex values with 0x as prefix. See section 3.3.2 p.12
- supports absolute time segments in mappings. See section 13.1.1 p.50
- `tempo` is now a floating point value
- fix touch events with edit dialog
- add 'inscore2' extension to files filter (mobile version)
- update to guido engine 1.66
- edit message supports `set` as argument. See section 3.6 p.15
- edit new `reset` argument to clear the edit string in the object cache. See section 3.6 p.15
- new `dshear` method. See section 3.2 p.10
- fix bug with javascript runtime variable (passed as argument to run)
- fix synchronization issue with arcs (not visible when synchronized)
- fix crash bug with `set` messages addressed to `/ITL/*/anobject`

20.5 Version 1.22 vs version 1.21

- new `opengl` message supported at scene level for optional OpenGL graphics rendering. Improves significantly the cpu use for graphics operations but at the cost of poorer rendering for text and symbolic scores
- fix potential issue with dates: dates expressed with big values for the numerator or the denominator may result in overflow

20.6 Version 1.21 vs version 1.18

- new set of sensor objects. See section 16 p.63.
- update to guido engine 1.63
- new `preprocess` message supported at application and scene level intended to debug javascript sections or math expressions. Output of pre-processing is printed to the log window. See section 9.1 p.37 and 10 p.42.
- environment variables introduced in scripting environment (OSName and OSId). See INScoreLang documentation.
- new math expressions introduced in scripting context. See INScoreLang documentation.
- new `syncFrame` synchronisation mode. See section 14.1.3 p.55 and 14.1.4 p.55.
- the `events` system has been extended to any object attribute and supports user defined events. This change comes also with a one tick delay introduced to handle all the events (i.e. the event associated messages are processed by the next time task): this is intended to avoid freezing the system in case of loops. See section 17.2 p.72 and 17.3 p.73.
- lua support has been dropped (compilation was optional, never embedded into a distribution)
- parser strategy changed: now each message is processed one by one to ensure the system consistency, especially for message based variables: an object state remains now consistent from one message to another.
- new `arc` object. See section 6.4 p.22 and 8.8 p.33.
- new `radius` message supported by rectangles. See section 8.7 p.33.
- new `edit` message supported by all objects: opens a small messages editor. See section 3.6 p.15.
- new `level` message supported by the log window and extended debugging support. See section 9.5.3 p.40.

- new video specific messages and management: the video time is now independent from the inscore object time. See section 8.5 p.32.
- `gmn objects set`: output correct error message in case of syntax error
- `save msg output changed`: a scene emit the `new` message, static info nodes (`log`, `stat`, `javascript...`)
- bug in `debug name` corrected (was not removed from graphic space)
- bug in `polygon` and `curve position` corrected (was not centered on 0 0) - use `/ITL` compatibility to preserve previous behaviour
- crash bug corrected: occurred when launching inscore from a secondary screen
- new `write` message supported by text based objects. See section 8.11.2 p.36.

20.7 Version 1.18 vs version 1.17

- new `tempo` message supported by all objects. See section 4.2 p.18.
- new `pageCount` event supported by symbolic score objects. See section 17.1.8 p.72.
- new `error` event supported at application level. See section 17.1.8 p.72.
- new `browse` message at application level to open a document in a web browser. See section 9.3 p.38.
- web api documentation included in package

20.8 Version 1.17 vs version 1.15

- support animated svg using the new `animate` message. See section 8.6 p.33.
- messages list variables are exported to javascript as a string.
- Carlito Regular open source font is embedded in the application resources and used as a default font. See at <https://fontlibrary.org/fr/font/carlito> for more information.
- symbolic notation support extended with score expressions. See section 18 p.78.
- new `newData` event. See section 17.1.7 p.71.
- the javascript engine is shared between the application and the different scenes. Note that it may change a script behavior when exploiting the previous independance of the javascript engine environments.
- new javascript `osname` function that gives the current operating system name. See INScoreLang documentation.
- new javascript `osid` function that gives the current operating system as an id. See INScoreLang documentation.
- `rootPath` message can be called without parameter to clear a scene `rootPath`. See section 10 p.42.
- `log window` supports the `foreground` message. See section 9.5.3 p.40.
- user actions on windows are generating `foreground` messages.
- application quit when the last scene is closed (even when the log window is opened)
- new `lock` message supported by all objects to prevent an object deletion. See section 3 p.7.
- OSC output buffer has been enlarged to 32768. Note that sending large messages works on localhost but are likely to face the MTU on real network.
- crash bug corrected: outgoing OSC messages are now handling buffer overflow exceptions.
- support for multi touch events. See section 17.1.2 p.70.
- new `radialgraph` signal representation. See section 15.3 p.60.
- `httpd` object is visible as a qrcode giving the server url.
- `httpd` object is now part of the library (not a plugin any more) (not available on Windows, Android and iOS)
- `frameless` and `fullscreen` modes management revised at view level and are now now exclusive at model level
- String without spaces in INScore scripts no longer need to be quoted.

20.9 Version 1.15 vs version 1.12

- new frame query method: `get frame` gives the coordinates of 4 points that represent the object frame, expressed in the scene local coordinates system and including all the graphic transformations (scaling, rotations on the 3 axis, shear etc.)
- pen messages are now accepted by all the components. This extension is provided to display any object bounding box. Note that for rects, ellipses etc. the previous behavior is preserved.
- pianoroll support. See section 6.2 p.21 and 8.4 p.30.
- Add web Api to expose inscore on the web with websocket or http.
- Add change tab on mobile with three digits gesture.
- add new object `filter` at application and scene level to filter forwarded messages.
- sending to broadcast address is enabled
- add `forward` and `filter` messages to the scene to handle messages forwarding at scene level. See section ?? p.??.
- default port to forward messages is now 7000.
- add new optional tab at startup with a menu for ios and android.
- add zoom and move capabilities at scene level using `scale`, `OSCxorigin` and `OSCyorigin`. This is intended to support two fingers gesture on mobile device.
- bug with lines corrected: a line in non-square parent was rotated when the parent's width was smaller than its height.
- bug with `eval` forwarding corrected: forwarded messages were triggering a syntax error due to a misinterpreted incorrect args count

20.10 Version 1.12 vs version 1.08

- line objects: `color` message is now an alias of `penColor`.
- `foreground` method at scene level to put a scene window in foreground. See section 10 p.42.
- text items support font spec with new `fontSize`, `fontFamily`, `fontStyle` and `fontWeight` messages. See section 8.11.1 p.35.
- new `compatibility` method at application level, provided to preserve previous behaviors. See section 9.1 p.37.
- default size of guido item is increased: the ratio to the previous size is 8.
- force default size and font to text items in order to get equivalent rendering on different platforms (default to Arial 13px).
- new `arrows` attribute for line objects. See section 8.10 p.34.
- the `export` message supports multiple file paths. See section 3 p.7.
- new `exportAll` message to export an object with its children. See section 3 p.7.
- incoming messages buffer size increased to 10.000
- url support for inscore files (`load` message)
- new common queries (`get message`): `count` and `rcount` that give the enclosed objects count and recursive count. The messages are supported at scene and application level as well. See section 10.3 p.43.
- new `memimg` object that capture the image of any object hierarchy including scenes. See section 6.6 p.23.
- supports relative OSC addresses that are evaluated in the context of the target object (i.e. a scene for drag and drop operations, arbitrary objects with the `eval` method).
- new `eval` method that takes a message list as argument, provided as a context for relative addresses evaluation. See section 5 p.19.
- new `httpd` object that implements an http server providing images of the scene to remote clients. See section 6.10 p.25 and section 19.3 p.87.
- new `websocket` object that implements a websocket server providing images of the scene to remote clients but also changes notifications. See section 6.10 p.25.
- Files objects can receive URL as path. See section 6.8 p.24.

- new intermediate object for the URL (waiting for the data to be downloaded to create the real object)
- new events associated to url based objects: success, error, cancel. See section 17.1.6 p.71.
- support for int values as parameters of the set method of rect shape and polygon objects
- the `clear` message addressed to a `gmnstream` object clears also the view. The change was not previously reflected until a new valid string was posted to the object.
- bug in export item corrected : child scaling was not applied.
- bug correction: for multiple exports, only the last one was done.
- bug in extended address support corrected: extended address was ignored for messages dropped to a scene .
- bug in window color corrected: black color was not correctly set due to an incorrect color information returned by Qt.
- bug with 'line' initialization corrected: wrong position and orientation with negative coordinates (was previously corrected but reintroduced), incorrect initialization in layers.

20.11 Version 1.08 vs version 1.07

- new `__END__` marker supported to end a script parsing at arbitrary location (see INScoreLang documentation.).
- when displaying the mapping, the map dates are not printed any more by default (due to size and collisions). The debug map parameter change from boolean to int value: 1 to activate the mapping display, 2 to have also the dates displayed (see section 8.12 p.36).
- the signal node is available at any level of the hierarchy (as well as the sync node)
- new `connect` and `disconnect` messages for the signal node to support signal connection to objects graphic attributes (see section 15.2 p.59).
- a slave can have several masters
- no more side effects for synchronized objects (position change, scaling)

20.12 Version 1.07 vs version 1.06

- bug with 'line' initialization corrected: wrong position and orientation with negative coordinates.
- new `plugins` static node at application level to provide a user path to look for pugins (see section 9.5.4 p.41).
- explicit objects for musicxml scores (`musicxml` and `musicxmlf` types) (see section 6.1 p.20).
- new `faustdsp` object, charging `libfaust` as a plugin to compile faust DSP on-the-fly (see section 6.5 p.23).
- exception caught when sending osc messages: was a potential crash, e.g. in case of `get` message sent to a signal with a large buffer -> out of buffer memory
- new javascript 'post' function for posting delayed messages (see INScoreLang documentation.)
- new `write` method supported by the 'log' window (see section 9.5.3 p.40)
- variable addresses are evaluated in message based variables
- supports relative rotations on x and y axis

20.13 Version 1.06 vs version 1.05

- `save` message can now take an optional list of attributes to be saved (see section 3 p.7)
- variables are now evaluated and expanded inside strings. Thus interaction variables can now be passed as argument of javascript functions.
- corrects musicxml-version output
- log window is put to front when the show menu is recalled
- object aliases are removed when the object is deleted

20.14 Version 1.05 vs version 1.03

- incorrect error message for watch messages corrected
- new javascript `readfile` function (see INScoreLang documentation.)
- log window is now available from the application 'Tools' menu
- new `brushStyle` attribute (see section 8.1 p.28)
- new `layer` object (see section 6.7 p.24)
- new `save` method specific to the log window: saves the window content to a file (see section 9.5.3 p.40)
- new `event` method supported at object level for UI events simulation
- new `del` watchable event: sent when deleting an object (see section 17.1.7 p.71)
- new `gmstream` guido stream object (see section 6.1 p.20)

20.15 Version 1.03 vs version 1.0

- log window utility provided as a new static node at application level (`/ITL/log`) (see section 9.5.3 p.40).
- new `systemCount` read only attribute for Guido scores (see section 8.3 p.30)
- IRCAM gesture follower support (see section 19.2 p.84)
- javascript engine is available at the static address `/ITL/scene/javascript` and can be activated using a 'run' method (see INScoreLang documentation.)
- new `export` event (see section 17.1.7 p.71)
- new `endPaint` event at scene level (see section 17.1.7 p.71)
- new `windowOpacity` method at scene level (see section 10 p.42)
- bug correction: error messages not generated for dropped files (actually for the scene load method)
- bug correction: possible infinite loop in `QStretchTilerItem::paint` method
- bug correction: incorrect get alias output (all the aliases were dumped out in a single message)

20.16 Version 1.00 vs version 0.98

- bug correction in stretching very small objects (due to approximations)
- bug correction in `$sx` and `$sy` computation (`xorigin` and `yorigin` was not taken into account)
- new 'ticks' message at application level for querying or setting the current count of time tasks (see section 9.1 p.37)
- new 'time' message at application level for querying or setting the current time (see section 9.1 p.37)
- new 'forward' message at application level for messages forwarding to remote hosts (see section 9.1 p.37)
- new 'relative | absolute' synchronization mode (see section 14.1 p.54)
- 'rename' message not supported any more
- a scene accepts multiple dropped files
- significant extension and syntax changes in inscore script files (see INScoreLang documentation.)
- `fileWatcher` methods renamed and simplified (see section 17.7 p.77)
- 'click' and 'select' messages are not supported any more.
- new 'stats' virtual node at application level (address `/ITL/stats`), supports 'get' and 'reset' messages the node gives statistics about the incoming messages (see section 9.5.2 p.40)
- crash bug in signal creation corrected: a signal size created with an incorrect stream (e.g. a string value) was 0 and no buffer was allocated.
- extension of the time related events to duration: new 'durEnter' and 'durLeave' watchable events (see section 17.1.3 p.70)
- new 'absolutexy' message at scene level to switch to absolute coordinates (in pixels) (see section 10 p.42)
- new 'push' and 'pop' messages to store and restore current watched events and associated messages (see section 17.6 p.76)

- internal change: mappings are now implemented as a separable library strictly complying to the mappings formalism.
- new %f format for the date variable to request a float value (instead a rational value) (see section 17.5.3 p.75).
- dates may be specified as rational strings (see section 4 p.17).
- interaction messages are not any more generated when the date can't be resolved.
- new rate message at application level to control the time task rate (see section 9 p.37)
- new frameless message at scene level to switch to frameless or normal window (see section 10 p.42)

20.17 Version 0.98 vs version 0.97

- new fastgraph object for graphic signals fast rendering (see section 6 p.20)
- \$date variable overflow caught
- files dropped on application icon correctly opened when the application is not running
- supports drag and drop of textual osc message strings
- osc error stream normalized: the message address is 'error:' or 'warning:' followed by a single message string.
- javascript and lua support: a single persistent context is created at application level and for each scene. (see section ?? p.??)

20.18 Version 0.97 vs version 0.96

- objects position, date and watched events preserved through type change
- bug in quantified dates corrected (null denominator set to the quantified value)
- new 'alias' message providing arbitrary OSC addresses support
- bug in parser corrected: \ escape only ' and " chars, otherwise it is literal
- guido score map makes use of the new guidolib extended mapping API for staff and system
- chords map correction (corrected by guido engine)

20.19 Version 0.96 vs version 0.95

- switch to v8 javascript engine
- lua not embedded by default

20.20 Version 0.95 vs version 0.92

- new 'mouse' 'show/hide' message supported at application level (see section 9 p.37)
- graphic signal supports alpha messages at object level
- javascript and lua embedded and supported in inscore scripts.
- bug correction in sync delete (introduced with version 0.90)

20.21 Version 0.92 vs version 0.91

- bug corrected: crash with messages addressed to a signal without argument
- date and duration messages support one arg form using 1 as implicit denominator value the one arg form accepts float values (see section 4 p.17).

20.22 Version 0.91 vs version 0.90

- bug in sync management corrected (introduced with the new sync parsing scheme)

20.23 Version 0.90 vs version 0.82

- at application level: osc debug is now 'on' by default
- new scripting features (variables).
- ITL file format change:
 - semicolon added at the end of each message
 - '/' comment not supported any more
 - '%' comment char replaced by '!'
 - new variables scripting features
 - single quote support for strings
 - messages addressed to sync node must use the string format
- new 'grid' object for automatic segmentation and mapping

20.24 Version 0.82 vs version 0.81

- new Faust plugins for signals processing
- colors management change: all the color models (RGBA and HSBA) accept now float values that are interpreted in the common [-1,1] range. For the hue value, 0 always corresponds to 'red' whatever the scale used.
- stretch adjustment for video objects (corrects gaps in sync h mode)
- support for opening inscore files on the command line
- system mapping correction
- splash screen and about menu implemented by the viewer

20.25 Version 0.81 vs version 0.80

- behavior change with synchronization without stretch: now the system looks also in the slave map for a segment corresponding to the master date.
- \$date variable change: the value is now (0,0) when no date is available and \$date is time shifted according to the object date.
- date message change: the date 0 0 is ignored

20.26 Version 0.80 vs version 0.79

- corrects the map not saved by the save message issue
- corrects get map output: 2D segments were not correctly converted to string

20.27 Version 0.79 vs version 0.78

- crash bug corrected for the 'save' message addressed to '/ITL'
- message policy change: relaxed numeric parameters policy (float are accepted for int and int for float)
- bug in get watch for time events corrected (incorrect reply)

Known issues:

- map not saved by the save message

20.28 Version 0.78 vs version 0.77

- `guido` system map extended: supports flat map or subdivided map (see section 13.4 p.52).
- new `shear` and `rotate` transformations messages (see section 3.2 p.10).
- new `rename` message to change an object name (and thus its OSC address) (see section 3 p.7).
- relaxed bool parameter policy: objects accept float values for bool parameters
- automatic numbering of exports when destination file is not completely specified i.e. no name, no extension. (see section 3 p.7).
- quantification introduced to `$date` variable (see section 17.5 p.74).
- `reset` message addressed to a scene clears the scene `rootPath`

20.29 Version 0.77 vs version 0.76

- `get guido-version` and `musicxml-version` messages supported by the application (see section 9 p.37).
- `save` message bug correction - introduced with version 0.70: only partial state of objects was saved
- `rootPath` message introduced at scene level (see section 10 p.42).
- scene name translation strategy change: only the explicit 'scene' name is translated by the scene load message handler into the current scene name, other names are left unchanged.
- bitmap copy adjustment in sync stretched mode is now only made for images

20.30 Version 0.76 vs version 0.75

- new `require` message supported by the `/ITL` node (see section 9 p.37).
- new event named `newElement` supported at scene level (see section 17.1.3 p.70).
- new `name` and `address` variables (see section 17.5 p.74).
- new system map computation making use of the new slices map provided by the `guidolib` version 1.42
- INScore API: the `newMessage` method sets now the message `src IP` to `localhost` With the previous version and the lack of `src IP`, replies to queries or error messages could be sent to undefined addresses (and mostly lost).
- bug corrected with `ellipse` and `rect` : integer graphic size computation changed to float (prevents objects disappearance with small width or height)
- bug in scene export: left and right borders could be cut, depending on the scene size corrected by rendering the `QGraphicsView` container instead the `QGraphicsScene`
- crash bug with `$date:name` corrected: crashed when there is no mapping named `name`.

20.31 Version 0.75 vs version 0.74

- new `map+` message (see section 13.2 p.51).
- the `click` and `select` messages are deprecated (but still supported). They will be removed in a future version.

20.32 Version 0.74 vs version 0.63

- new `dpage` message accepted by `gmn` objects (see section 8.3 p.30).
- `x` and `y` variables: automatic range type detection (int | float)
- `set txt` message: accepts polymorphic stream like parameters (see section 6 p.20).
- drag and drop files support in INScore viewer
- interaction variables extension: `$sx`, `$sy` variables added to support scene coordinate space (see section 17.5 p.74).
- automatic range mapping for `$x`, `$y` variables.

- new `$self` and `$scene` variables in the address field (see section 17.5.7 p.76).
- OSC identifiers characters set extended with `'_'` and `'-'` (see section 2 p.3).
- support for multiple scenes: `new`, `del` and `foreground` messages (see section 10 p.42).
- `load` message supported at scene level (see section 10 p.42).
- `get watch` implemented.
- `watch` message without argument to clear all the watched events (see section 17.5 p.74).
- order of rendering and width, height update corrected (may lead to incorrect rendering)
- bug with `gmn` score corrected: missing update for page, columns and rows changes.
- package delivered with the Guido Engine version 1.41 that corrects minimum staves distance and incorrect mapping when optimum page fill is off.

20.33 Version 0.63 vs version 0.60

- new `'mousemove'` event (see section 17.1.1 p.69).
- interaction messages accept variables (`$x`, `$y`, `$date...`) (see section 17.5 p.74).
- SVG code and files support (see section 6.9 p.25).
- set line message change: the `x y` form is deprecated, it is replaced by the following forms: `'xy' x y` (equivalent to the former form) and `'wa' width angle` (see section 6 p.20).
- new `'effect'` message (section 3.5 p.14).
- utf8 support on windows corrected
- transparency support for stretched synchronized objects corrected
- multiple application instances supported with dynamic udp port number allocation.
- command line option with `-port portnumber` option to set the receive udp port number at startup.

20.34 Version 0.60 vs version 0.55

- new `'xorigin'` and `'yorigin'` messages (section 3.1.3 p.10).
- new interaction messages set (section 17 p.68).
- alpha channel handled by images and video
- bug correction in line creation corrected (false incorrect parameter returned)
- bug correction in line `'get'` message handling
- memory leak correction (messages not deleted)

Known issues:

- incorrect graphic rendering when `'sync a b'` is changed to `'sync b a'` in the same update loop
- incorrect nested synchronization when master is horizontally stretched,

20.35 Version 0.55 vs version 0.53

- ITL parser corrected to support regexp in message string (used by messages addressed to sync node)
- format of mapping files and strings changed (section 13.1 p.49).
- format of sync messages extended to include map name (section 14 p.53).
- signal node: `'garbage'` message removed
- new `'reset'` message for the scene (`/ITL/scene`) (section 10 p.42).
- new `'version'` message for the application (`/ITL`) (section 9 p.37).
- new `'reset'` message for signals (section 15.1.1 p.57).
- bug parsing messages without params corrected
- slave segmentation used for synchronization

- new H synchronization mode (preserves slave segmentation)
- crash bug corrected for load message and missing ITL files

20.36 Version 0.53 vs version 0.50

- Graphic signal thickness is now symmetrically drawn around y position.
- ITL file format supports regular expressions in OSC addresses.
- IP of a message sender is now used for the reply or for error reporting.
- new `line` object (section 6 p.20).
- new `penStyle` message for vectorial graphics (section 8 p.28).
- new color messages `red`, `green`, `blue`, `alpha`, `dcolor`, `dred`, `dgreen`, `dblue` (section 3 p.7 and 3.1.2 p.9).
- color values for objects are bounded to [0,255]
- `get map` message behaves according to new `map` message (section 7 p.27).
- `get width` and `get height` is now supported by all objects (section 7 p.27).
- bug in signal projection corrected (index 0 rejected)
- bug in signals default value delivery corrected
- new `pageCount` message for guido scores
- debug nodes modified state propagated to parent node (corrects the debug informations graphic update issue)
- rational values catch null denominator (to prevents divide by zero exceptions).

20.37 Version 0.50 vs version 0.42

- identifier specification change (section 2 p.3).
- new `application hello` and `defaultShow` messages (section 9 p.37).
- new `load` and `save` messages (sections 9 p.37 and 3 p.7).
- `click` and `select` messages:
 - `rightbottom` and `leftbottom` modes renamed to `bottomright` and `bottomleft`
 - new `center` mode for the `click` message
 - query mode sent back with the reply both for `click` and `select` messages
- new `file`, `html` and `htmlf` types for the `set` message (section 6 p.20).
- `get` syntax change for the `scene`.
- `fileWatcher` messages completely redesigned.
- mappings can be identified by names (section 13.1 p.49).
- `rect`, `ellipse`, `curve`, `line` and `polygon` object support graphic to relative-time mapping
- new synchronization modes for Guido scores: `voice1`, `voice2`, ... , `staff1`, `staff2`, ... , `system`, `page`.
- Guido mapping manages repeat bars.
- Graphic signals messages design (section 15.3 p.60).